



Mimer SQL

OpenVMS Guide

Version 11.0

Mimer SQL, OpenVMS Guide, Version 11.0, September 2025
© Copyright Mimer Information Technology AB.

The contents of this manual may be printed in limited quantities for use at a Mimer SQL installation site. No parts of the manual may be reproduced for sale to a third party.
Information in this document is subject to change without notice. All registered names, product names and trademarks of other companies mentioned in this documentation are used for identification purposes only and are acknowledged as the property of the respective company. Companies, names and data used in examples herein are fictitious unless otherwise noted.

Produced and published by Mimer Information Technology AB, Uppsala, Sweden.

Mimer SQL Web Sites:
<https://developer.mimer.com>
<https://www.mimer.com>

Contents

.....	i
Introduction.....	1
About Mimer SQL for OpenVMS.....	1
The Mimer SQL Database Server	1
Embedded SQL.....	1
Module SQL.....	2
JDBC Driver.....	2
ODBC Driver.....	2
Mimer SQL C API	2
Mimer SQL Python Adapter.....	2
Utilities.....	3
OpenVMS System Requirements	4
Documentation Resources.....	4
Documentation Conventions	4
Terms and Definitions	5
Installing Mimer SQL	7
Overview	7
Execute the distribution file to obtain the installation files	7
Use PRODUCT INSTALL to install Mimer SQL.....	8
Add commands in system startup files	8
Execute SYS\$MANAGER:MIMER\$SETUP_xxxxx.COM for this process	9
Install your Mimer SQL license key	9
The SYS\$MANAGER:MIMER\$SETUP_xxxxx command procedure	9
Logical Names Defined by SETUP	10
Installing the Mimer SQL License Key	11
Mimer SQL for OpenVMS in Production.....	11
The MIMLICENSE Utility.....	11

Removing a Mimer SQL Installation	12
Establishing a Database	15
Overview	15
Creating a Home Directory	15
Editing the SQLHOSTS File	15
Adding a Local Database	16
Specifying the Default Database	16
Generating System Databanks and SYSADM.....	17
SDBGEN	17
Generating the System Databanks	18
Accessing a Remote Database	19
Adding a Remote Database.....	20
Mimer SQL System Settings	20
Automatic Database Server Start.....	20
Automatic Database Server Shutdown	20
Removing a Mimer SQL Database	21
Managing a Database Server.....	23
The MIMCONTROL Command	23
Database Server Parameters – the MULTIDEFS File	23
MIMCONTROL Syntax.....	24
MIMCONTROL (/STATUS/DCL).....	25
The MIMPERF Command.....	26
The MIMTCP Server.....	27
Controlling MIMTCP servers.....	28
Using a Memory Resident Buffer Pool	29
Determining Buffer Pool Size.....	30
Process Quotas for the Database Server.....	30
Troubleshooting Tips.....	30
Running Mimer BSQL Scripts	33
Running a BSQL Script.....	33
Building Mimer Applications on OpenVMS.....	35
Building example programs	36
Using the JDBC Driver	37
Using the JDBC Driver	37
Defining Java Commands	37
Setting CLASSPATH	37
Verifying the Environment	38
Testing the Connection.....	38
Distributed Files	41
Files in System Directories	41

Files in the Mimer Root Directory	42
Documentation Files (MIMER\$DOC)	42
Example Files (MIMER\$EXAMPLES)	43
Executable Programs (MIMER\$EXE)	44
Library Files (MIMER\$LIB)	46
Using x86 Cross-Compiling Tools with Mimer	47
Installing MIMERX86LIB on Itanium	47
Distributed files	48
Using the cross-compiler tools with Mimer	49
Index	51

Chapter 1

Introduction

This guide describes how to install and use version 11.0 of the Mimer SQL relational database server under OpenVMS. It contains OpenVMS specific instructions about installing the software, creating databases and managing database servers and is for general users, system administrators and programmers who use Mimer SQL on the OpenVMS operating system.

About Mimer SQL for OpenVMS

You can download a full version of Mimer SQL for OpenVMS for free from <https://developer.mimer.com/downloads>. This distribution is for evaluation only and it contains a complete copy of Mimer SQL Version 11.0, bundled with an evaluation license file.

The license key is limited in number of users. A customized license key can be received for free, either it will come separately along with the installation, or it can be ordered from the Mimer SQL Support desk (info@mimer.com).

Mimer SQL Run-time License

To use Mimer SQL for OpenVMS in production, you need a run-time license key.

Please contact your local Mimer representative, see <https://www.mimer.com/contact/>, or send an e-mail to info@mimer.com.

The Mimer SQL Database Server

The Mimer SQL database server is a single, multi-threaded process. By using DECThreads, good SMP scalability is achieved.

Clients using TCP/IP or Decnet can access the server. For clients running on the same host as the server, a special shared-memory based communication method is used.

Embedded SQL

An embedded SQL preprocessor is included. It enables SQL commands to be embedded in programs written in C/C++, Fortran and COBOL. The embedded syntax complies with the ISO standard for embedded SQL.

Module SQL

MSQL (Module SQL) enables you to call SQL statements in a host program written in C/C++, COBOL, Fortran or Pascal, without embedding the actual SQL statements in the host program. The SQL statements are explicitly put into a separate SQL module, that is written in the Module language and maintained separately from the host program.

JDBC Driver

A JDBC driver is included in the distribution. The driver is a type 4 driver, which means that it is written entirely in Java. This provides the driver with full portability so that it can be copied or downloaded to any Java-enabled platform. The driver uses TCP/IP to access a Mimer SQL server on any platform.

By using a special connection URL, the JDBC driver can also load a native library (`MIMER$LIB:MIMCOMM.EXE`). This allows the JDBC driver to use native code for all communication methods which can improve the performance.

The driver, `MIMJDBC3.JAR`, supports the JDBC 3 standard, and is for Java 1.4 or later.

ODBC Driver

The Mimer ODBC driver is a client library that enables applications to access Mimer database servers running on any platform. The driver complies with the ODBC 3.52 specification.

By using the ODBC driver on OpenVMS, you can develop ODBC applications and execute them on the OpenVMS platform.

Unlike other platforms, OpenVMS does not include a Driver Manager that enables OpenVMS applications to dynamically load drivers for different database products. Until such a Driver Manager becomes available on OpenVMS, you can link your applications directly to the Mimer ODBC driver.

Note that in order to run an ODBC application on a Windows platform, the Windows ODBC driver has to be installed on the client side. This driver can then access Mimer database servers on any platform (including OpenVMS). There is no need to install any special software on the server side in order to use ODBC.

Mimer SQL C API

The native Mimer SQL C API is included in the distribution. This API is intended for programs written in C and is described further in the *Mimer SQL Programmer's Manual*.

Mimer SQL Python Adapter

MimerPy is an adapter for Mimer SQL in Python which implements the Python Database API specification (PEP 249).

More information can be found on the Mimer Developer web site,
<https://developer.mimer.com/article/mimer-sql-python-adapter/>

Utilities

Mimer SQL includes the following utilities:

Utility	Description
BSQL	BSQL executes SQL statements which are entered interactively or read from a command file. It is described in the <i>Mimer SQL User's Manual</i> .
DBANALYZER	A tool to provide optimization recommendations for a database schema.
DBC	DBC checks if a databank file is internally consistent. It is described in the <i>Mimer SQL System Management Handbook</i> .
DBOPEN	DBOPEN opens and restarts all databanks in a database. It is described in the <i>Mimer SQL System Management Handbook</i> .
ESQL	ESQL is a pre-processor for embedded SQL.
EXLOAD	Utility to load the example database. See <i>Mimer SQL System Management Handbook</i> .
MIMCONTROL	MIMCONTROL provides facilities for managing the operation of a database server, for example, starting, controlled shutdown, etc.
MIMINFO	MIMINFO displays status information for a database server.
MIMLICENSE	Utility for managing Mimer SQL licenses.
MIMLOAD	Utility to load or unload data from the database. See <i>Mimer SQL System Management Handbook</i> .
MIMPERF	Utility to display performance counters in the server. Can be used interactively or together with the T4 tool.
MIMREPADM	Administration utility for Mimer Replication.
MIMSYNC	Utility to bring two replicated Mimer systems back into sync.
MSQL	MSQL is a pre-processor for Module SQL.
REPSERVER	Replication server.
SDBGEN	SDBGEN generates the Mimer SQL system databanks SYSDB, TRANSDB, LOGDB and SQLDB.
SQLMONITOR	Utility to display how the current SQL statements are using the server resources.
SQLTRANSLATOR	SQLTRANSLATOR can translate SQL statements from a non-compatible SQL syntax to valid Mimer SQL syntax.
TCPCONTROL	Procedure to manage MIMTCP processes.

The Mimer SQL distribution also contains examples of database programs and SQL statements. See *Appendix A Distributed Files* for more information.

OpenVMS System Requirements

On Itanium

OpenVMS V8.4-2L3 or later is required.

On x86_64

OpenVMS V9.2-3 or later is required.

To use the cross-compiler tools on Itanium to develop Mimer programs for x86_64, you need to install the separate product `MIMERX86LIB`, described in *Appendix B Using x86 Cross-Compiling Tools with Mimer*.

Documentation Resources

You can find relevant information in the OpenVMS System Management Guide (published by VSI). Most OpenVMS manuals can be found at <https://docs.vmssoftware.com/>

You should be familiar with the concepts and facilities provided by the Mimer SQL system.

Other documents that are referred to in this document or that may be of interest when dealing with the tasks described here are: the *Mimer SQL System Management Handbook*, the *Mimer SQL Programmer's Manual*, and the *Mimer SQL Release Notes*.

You can find them at <https://developer.mimer.com/documentation/>

The documentation is also included in the Mimer SQL distribution as PDF (Adobe Portable Document Format) files. After a SETUP has been made with an installed Mimer version, the documentation can be found in the directory pointed to by the logical name `MIMER$DOC`.

Documentation Conventions

Convention	Example	Explanation
All uppercase	COMMIT	Indicates command names, SQL reserved words, and keywords.
Monospace	\$ MIMCONTROL/START DB5	Indicates directory names, file names, code examples and interactive screen displays.
[]	[timeout]	Encloses optional items.

Convention	Example	Explanation
[]		Vertical bars separating optional items indicate that you can choose none, one or more than one item.
<i>Italics</i>	<i>Mimer SQL User's Guide</i>	Indicates a cross reference or the title of a guide.

Terms and Definitions

The following terms and acronyms are used in this document:

Term	Explanation
API	Application Programming Interface.
BSQL	BSQL, a program used to execute SQL statements which are read from a command file or entered interactively.
Data source	ODBC term for a database.
Databank	Databank is the Mimer SQL term for the physical file in which one or more Mimer SQL tables are stored. A databank corresponds to one file in the operating system. A database may contain several databanks.
Database	A database is a collection of databanks, tables, shadows, etc., all defined as objects in the data dictionary. A computer may have several databases operating simultaneously, but no information is shared between them. Each database has a unique name, registered in the SQLHOSTS file.
Database home directory	The directory where the SYSDDB databank file is located, also recorded in the SQLHOSTS file.
DCL	Digital Command Language.
Dynamic SQL	SQL statements constructed at runtime and passed to the database management system for execution.
Embedded SQL	The term used for SQL statements when they are embedded in a traditional host language.
ESQL	The preprocessor for embedded SQL.
Java	A platform independent language invented by Sun and now owned by Oracle. See https://www.oracle.com/technetwork/java/index.html .
JDBC	Java DataBase Connectivity. A set of Java interfaces for accessing relational databases. See https://www.oracle.com/technetwork/java/javase/jdbc/index.html .
MIMERxxxx	Symbolic name for the installed directory tree, unique for each Mimer SQL release, where 'xxxx' stands for the current version number, e.g. '1109E'.

Term	Explanation
MSQL	The preprocessor for Module SQL.
ODBC	Open Database Connectivity, a specification for a database API in the C language, independent of any specific DBMS or operating system.
PSM	Persistent Stored Modules, the term used by ISO/ANSI for stored procedures.
Shadow	<p>A shadow is a copy of the original (master) databank and is continuously updated by Mimer SQL.</p> <p>A Mimer SQL databank may have one or more shadows. If the databank is shadowed, there will be one file for each shadow. If the master databank is lost, it is possible to continue operations from the shadow databank without stopping the database server. A databank must have the TRANS or LOG option to be shadowed. For more information, see the <i>Mimer SQL System Management Handbook</i>.</p>
SQL	Structured Query Language, standardized language for database manipulation.
SQLHOSTS	<p>A file containing lookup information for all accessible Mimer SQL databases, relative to the current node.</p> <p>It is located at <code>SYS\$MANAGER:SQLHOSTS.DAT</code>.</p>
Table	Tables (or relations) hold all the information in a relational database. A table is stored in a databank. It may not be split across databanks, but a databank may contain several tables.

Chapter 2

Installing Mimer

SQL

This chapter describes how to install the Mimer SQL software on OpenVMS. It also documents how to remove a Mimer SQL installation.

Overview

- Execute the distribution file to obtain the installation files
- Use PRODUCT INSTALL to install Mimer SQL
- Add commands in `SYS$MANAGER:SYSTARTUP_VMS.COM`, `SYS$MANAGER:SYSHUTDWN.COM` and `SYS$MANAGER:SYLOGIN.COM`
- Execute `SYS$MANAGER:MIMER$SETUP.COM` to define Mimer commands for this process
- Install your Mimer SQL license key

Execute the distribution file to obtain the installation files

The software is distributed as a self-extracting ZIP file. The file is named `MIMERXXXXX-I64.ZIPEXE` for the Itanium version, and `MIMERXXXXX-X86.ZIPEXE` for the x86_64 version. To unpack the ZIP file, just execute it. The installation files will be extracted and placed in the current directory.

```
$ run mimer1109e-i64.zipexe
UnZipSFX 6.00 of 20 April 2009, by Info-ZIP (http://www.info-zip.org).
  inflating: MIMER-I64VMS-MIMER1109E-U1100-9E-1.PCSI$COMPRESSED
  inflating: mimer-i64vms-mimer1109e-u1100-9e-1.pcsi$compressed_VNC
```

Use PRODUCT INSTALL to install Mimer SQL

Use the command `PRODUCT INSTALL` to install Mimer SQL, just like any other layered product. Please note that the product name includes the version number which is unusual. New versions of Mimer will have new version numbers in the product name which will make all versions of Mimer to appear as different products. This allows multiple versions to be installed at the same time on a machine. The user can select any version by running its `SETUP` command procedure.

```
$ product install mimer1109e

Performing product kit validation of signed kits ...
%PCSI-I-VSIVALPASSED, validation of DKA100:[000000]MIMER-I64VMS-MIMER1109E-
U1100-9E-1.PCSI$COMPRESSED;1 succeeded

The following product has been selected:
  MIMER I64VMS MIMER1109E U11.0-9E           Layered Product

Do you want to continue? [YES]

Configuration phase starting ...

You will be asked to choose options, if any, for each selected product and for
any products that may be installed to satisfy software dependency
requirements.

Configuring MIMER I64VMS MIMER1109E U11.0-9E: Mimer SQL for OpenVMS

Copyright © 2025 Mimer Information Technology AB. All rights reserved.

Produced by Mimer Information Technology AB

A limited development license is included

* This product does not have any configuration options.

Execution phase starting ...

The following product will be installed to destination:
  MIMER I64VMS MIMER1109E U11.0-9E           DISK$VSI84-2:[VMS$COMMON.]
  Portion done:
  0%...10%...20%...30%...40%...50%...60%...70%...80%...90%...100%

The following product has been installed:
  MIMER I64VMS MIMER1109E U11.0-9E           Layered Product

  MIMER I64VMS MIMER1109E U11.0-9E: Mimer SQL for OpenVMS

  Insert the following lines in SYS$MANAGER:SYSTARTUP_VMS.COM:
    @SYS$STARTUP:MIMER$STARTUP_1109E
  Insert the following lines in SYS$MANAGER:SYSHUTDWN.COM:
    @SYS$STARTUP:MIMER$SHUTDOWN_1109E

  Users need to add the following lines to their login command procedure:
    $ @SYS$MANAGER:MIMER$SETUP_1109E VMS
```

Add commands in system startup files

As instructed by the `PRODUCT INSTALL` command, you should add commands to execute Mimer startup and shutdown procedures.

The procedure `SYS$STARTUP:MIMER$STARTUP_1109E` installs required shareable images. Add a command to do this in `SYS$MANAGER:SYSTARTUP_VMS.COM`.

The procedure `SYS$STARTUP:MIMER$SHUTDOWN_1109E` deinstalls shareable images. Add a command to do this in `SYS$MANAGER:SYSHUTDWN.COM`.

Any process that is running Mimer SQL must execute the `SETUP` command procedure for the version of Mimer SQL it wants to use. By adding the `SETUP` command in `SYS$MANAGER:SYLOGIN.COM`, a default `SETUP` is provided for all processes. This makes it easier to manage a version upgrade of Mimer SQL since the command is in a central place.

Execute `SYS$MANAGER:MIMER$SETUP_xxxxx.COM` for this process

To continue using the newly installed Mimer SQL product in the current process you should execute the `SETUP` procedure.

```
$ @SYS$MANAGER:MIMER$SETUP_1109E VMS
```

An alternative is to log out and log in again. The new process should have executed the `SYS$MANAGER:SYLOGIN.COM` procedure where you have added the `SETUP` command.

The `SETUP` procedure is described further in section *The `SYS$MANAGER:MIMER$SETUP_xxxxx` command procedure* on page 9.

Install your Mimer SQL license key

Mimer requires a license key to be installed. A license for evaluation purposes is included in the Mimer distribution and is found in `MIMER$EXAMPLES:DEFAULTKEY.MCFG`. When Mimer is installed, this default key is installed automatically.

If you need to install a new license use the `MIMLICENSE` command.

The `MIMLICENSE` command is described further in section *Installing the Mimer SQL License Key* on page 11.

```
$ MIMLICENSE /FILE=MIMER$EXAMPLES:DEFAULTKEY.MCFG
License key file: SYS$SPECIFIC:[SYSMGR]MIMERKEY_IA64.DAT

Number Expires      Version Module      Users Netusers
----- -----      ----- -----
-6 2028-09-30 11.0      Mimer SQL      2      2 *** evaluation
                           XA
Key file updated
```

Note: The database server must be restarted to enable the new key settings

The `SYS$MANAGER:MIMER$SETUP_xxxxx` command procedure

Use the `MIMER$SETUP_xxxxx` procedure found in `SYS$MANAGER` to select a Mimer version. The procedure defines logical names and defines commands for the current process. For example:

```
$ @SYS$MANAGER:MIMER$SETUP_1109E VMS
```

@SYS\$MANAGER:MIMER\$SETUP_1109E VMS

This command specifies that Mimer version 11.0.9E should be used. Logical names are defined in the process logical name table. Mimer commands are defined in VMS style (like: MIMCONTROL/ START).

Note that if you create a subprocess (by using the SPAWN command), the command definitions will not be active in the there. Use the SETUP command again in the subprocess.

If no parameter is given to the SETUP procedure, VMS will be assumed.

@SYS\$MANAGER:MIMER\$SETUP_1109E UNIX

This command specifies that Mimer version 11.0.9E should be used. Logical names are defined in the process logical name table. Mimer commands are defined in UNIX style (like: mimcontrol --start).

UNIX command definitions will be transferred to any subprocess you start with the SPAWN command.

@SYS\$MANAGER:MIMER\$SETUP_1109E CLEAR

Clears all logical names and command definitions made by an earlier invocation of the SETUP procedure.

Logical Names Defined by SETUP

The SETUP command defines the logical names listed below

Logical name	Description
MIMER\$ROOT	Points to the Mimer installation directory, such as SYS\$COMMON: [MIMER1109E]
MIMER_SQLHOSTS	Points to the file defining database names
MIMER\$LIB	Location of header files, etc
MIMER\$DOC	Location of Mimer documentation
MIMER\$EXAMPLES	Directory containing example files
MIMER\$EXE	Location of Mimer executable files
MIMER\$SQL	Specifies selected version of MIMER\$SQL image
MIMER\$ODBC	Selected version of MIMER\$ODBC image
MIMER\$API	Selected version of MIMER\$API image
MIMER\$DBP	Points to shareable image for shared memory communication
MIMCOMM	Selected version of MIMCOMM image
MIMCOMM64	Selected version of MIMCOMM64 image

Installing the Mimer SQL License Key

The included evaluation license key is exclusively for evaluation. This means that, as long as you use Mimer SQL for evaluation, you can set up a complete Mimer SQL environment and work with Mimer SQL without adding any additional license keys, but if you want to use Mimer SQL in a development environment you will need a production license.

Mimer SQL for OpenVMS in Production

If you want to use Mimer SQL in production, you must purchase a valid run-time license key and then install it. Please contact your local Mimer SQL representative, see <https://www.mimer.com/contact/>, or send an e-mail to info@mimer.com.

Node Name

Your representative will need to know the node name of the computer on which the Mimer SQL database server will run.

To obtain the node name, use `MIMLICENSE/CPUID`:

```
$ MIMLICENSE/CPUID
GOOFY VMS IA64
```

Receiving Your Run-time License Key

Your run-time license key and instructions for installing it will be e-mailed to you.

When you receive the file, save it in an accessible directory.

The `MIMLICENSE` Utility

You use the `MIMLICENSE` utility to administrate the license key file. You can add, remove and update keys using `MIMLICENSE`.

You can also use `MIMLICENSE` to list and describe the contents of the key file.

Note: When entering the Mimer SQL license key, you must have appropriate access to the key file.

Adding a License Key using `MIMLICENSE`

To add a license key

- 1 Assuming a `SETUP` with VMS-style commands, enter the following:

```
$ mimlicense /FILE=file_name.mcfg
```

For example, if the license key file you received was named `mimerkey1234.mcfg`, you would enter the following:

```
$ mimlicense /FILE=mimerkey1234.mcfg
```

MIMLICENSE Syntax

The MIMLICENSE program is controlled by options specified on the command-line.

Argument	Function
/ADD= <i>hexcode</i>	Adds a license key.
/COMBINED	Describes what the combined keys permits.
/CPUID	Show the CPU id of the machine.
/DELETE= <i>key-id</i>	Deletes the specified key.
/FILE= <i>file-name</i>	Adds a license key from a .mcfg file.
/LIST	Lists the contents of the key file.
/NOLOGO	Silent mode, i.e. execution with no output.
/REMOVE	Removes all keys. (Each key must be verified.)
/VERSION	Show version number of the MIMLICENSE command.

The Mimer SQL license keys are stored in the file

SYS\$SPECIFIC: [SYSGR] MIMERKEY_IA64.DAT or MIMERKEY_X86_64.DAT, depending on platform.

Removing a Mimer SQL Installation

Caution: If you plan to remove any Mimer SQL databases, see *Removing a Mimer SQL Database* on page 21 **before** removing the Mimer SQL installation.

To remove a Mimer SQL installation:

- 1 Check that no Mimer SQL applications or database servers are using the installation.
- 2 Remove the selected Mimer SQL version by using the PRODUCT REMOVE command:

```
$ PRODUCT REMOVE MIMER1109E

The following product has been selected:
      MIMER I64VMS MIMER1109E U11.0-9E          Layered Product

Do you want to continue? [YES]

The following product will be removed from destination:
      MIMER I64VMS MIMER1109E U11.0-9E          DISK$VSI84-2:[VMS$COMMON.]
      Portion done:
      0%...10%...20%...30%...40%...50%...60%...70%...80%...90%...100%

The following product has been removed:
      MIMER I64VMS MIMER1109E U11.0-9E          Layered Product
```

- 3 If there are no other Mimer SQL installations in the system, you may want to delete the SQLHOSTS file and the Mimer SQL license key file:

```
$ DELETE SYS$SPECIFIC:[SYSMGR]SQLHOSTS.DAT.*  
$ DELETE SYS$SPECIFIC:[SYSMGR]MIMERKEY_*.DAT.*
```

- 4 If you have added any Mimer SQL-related or database-specific commands to the OpenVMS startup files, you need to remove them. Look in:

```
SYS$MANAGER:SYSTARTUP_VMS.COM  
SYS$MANAGER:SYSHUTDWN.COM  
SYS$MANAGER:SYLOGIN.COM
```


Chapter 3

Establishing a Database

This chapter describes how to establish a local database and how to access a remote database already established in the network. It also describes how to upgrade and remove a database.

Refer to the *Mimer SQL System Management Handbook* for background information which is useful for understanding the issues and the different components involved in establishing a Mimer SQL database.

Overview

Having installed Mimer SQL, you can now establish a local database on the node on which you unpacked the Mimer SQL distribution.

To establish a database on an OpenVMS node, you must carry out the following steps:

Step 1 Create a home directory for your Mimer SQL database

See *Creating a Home Directory* on page 15.

Step 2 Prepare access to the database by editing the SQLHOSTS file

See *Editing the SQLHOSTS File* on page 15.

Step 3 Run SDBGEN to generate the system databanks and the SYSADM ident

See *Generating System Databanks and SYSADM* on page 17.

Creating a Home Directory

First of all you must create a home directory for your database, for example:

```
$ CREATE/DIR somedisk:[TESTDB]
```

Editing the SQLHOSTS File

The SQLHOSTS file is used to list all the databases that are accessible to a Mimer SQL application from the node on which it is installed.

On a VMS node, the SQLHOSTS file is located by translating the logical name MIMER_SQLHOSTS.

The SETUP command will define it to be:

```
SYS$SPECIFIC:[SYSTMGR]SQLHOSTS.DAT
```

A default SQLHOSTS file is installed the first time you run SETUP.

The SQLHOSTS file contains three sections:

- **LOCAL**

The LOCAL section contains the names of the local databases on the current node, see *Adding a Local Database* on page 16.

- **REMOTE**

The REMOTE section contains the names of remote databases accessible from the node, see *Accessing a Remote Database* on page 19.

- **DEFAULT**

One of the local or remote databases can be set to be the default database for the node by specifying its name in the DEFAULT section, see *Specifying the Default Database* on page 16.

Note: In the SQLHOSTS file, a line of text beginning with the character sequence -- is interpreted as a comment.

The maximum length for the name of a database on an OpenVMS node is 30 characters.

Adding a Local Database

To add a local database:

- 1 Open the SQLHOSTS file in a text editor and locate the LOCAL section.
- 2 Under Database, enter the name of the database.
- 3 Under Path, enter the name of the directory which is to be the database's home directory.

Example of a LOCAL Entry

```
LOCAL:
--
-- Database      Path
--- -----
TESTDB          DISK:[TESTDB]
-----
```

Specifying the Default Database

The DEFAULT section in the SQLHOSTS file contains a single line that specifies the default database. This is the database which will be used if a database is not explicitly specified when logging on.

The default database must be listed in either the LOCAL or the REMOTE section.

Example of a Default Entry

```
DEFAULT:  
--  
-- Database  
=====  
TESTDB  
=====
```

Generating System Databanks and SYSADM

You generate the Mimer SQL system databanks SYSDB, TRANSDB, LOGDB and SQLDB by running the SDBGEN program.

When you run SDBGEN, it also generates the system administration ident SYSADM.

SDBGEN loads the system tables and defines the data dictionary views detailed in the *Mimer SQL Reference Manual*.

Note: A databank created for one SYSDB cannot be accessed by using a different SYSDB even if identical data dictionary definitions are created in it.

SDBGEN

The SDBGEN command has two purposes. Either to create a new set of system databank files, or to upgrade database files created in an earlier version of Mimer SQL to version 11.0. Upgrade can be done for databank files created by Mimer SQL version 10.1 only.

For more information on upgrading, see *Mimer SQL Release Notes*.

SDBGEN Syntax

Assuming a SETUP is done with VMS-style commands, you run SDBGEN from the command line, using arguments.

The syntax for creating databank files is as follows:

```
SDBGEN [/PASSWORD=password] [dbase] [syssz] [tfn] [tsz] [lfn] [lsz] [sfn] [ssz]
```

sdbgen Command-line Arguments

Argument	Function
/PASSWORD=password	Password for SYSADM
dbase	Database name
syssz	Size of SYSDB
tfn	Filename for TRANSDB
tsz	Size of TRANSDB
lfn	Filename for LOGDB
lsz	Size of LOGDB
sfn	Filename for SQLDB
ssz	Size of SQLDB

Generating the System Databanks

For example, the following SDBGEN call:

```
$ SDBGEN /PASSWORD=oops TESTDB
```

will generate a database named `my_database` and the database administration ident `SYSADM` will be assigned the password `oops`.

If you do not enter the `password` parameter, SDBGEN will prompt you for all parameters that are missing, including the password for `SYSADM`.

If you enter the `password` parameter, SDBGEN will not prompt for any missing parameters, it will use default values.

If you do not enter the `dbase` parameter, the environment variable `MIMER_DATABASE` is used to determine which database the databank files should be created for.

Setting the Initial Size

You can specify the initial size for each of the Mimer SQL system databanks.

The size for the databanks is specified in Mimer SQL pages. The size of a Mimer SQL page is 4 kilobytes.

SYSADM Password

When you run SDBGEN, the database administration ident `SYSADM` is created and you must specify a password (passwords are case-sensitive) for this ident.

SYSADM Password Case

If your process uses TRADITIONAL parsing, DCL converts all VMS-style commands to uppercase and all Unix-style commands to lowercase. To control the case used in your password, you may have use quotes.

If your process uses EXTENDED parsing, DCL does not convert command arguments to uppercase.

For more information on `PARSING_STYLE`, use `HELP`:

```
$ HELP SET PROCESS/PARSE_STYLE
```

The following table shows how to use quotes to set the password case if TRADITIONAL parsing is used.

Entering:	Sets the password to:
<code>SDBGEN/PASS=oops</code>	<code>OOPS</code>
<code>SDBGEN/PASS="oops"</code>	<code>oops</code>
<code>SDBGEN -p OOPS</code>	<code>oops</code>
<code>SDBGEN -p "OOPS"</code>	<code>OOPS</code>

SYSADM Password Security

For security reasons, the password specified for SYSADM is not echoed on the screen when you enter it.

You should change the password at appropriate intervals using Mimer SQL with the `ALTER IDENT` statement.

Caution: Take care to safeguard the SYSADM password, because if it is lost, it cannot be retrieved from the system and it is not possible to set a new one.

Accessing a Remote Database

You can access databases that reside on other nodes on the network by editing the REMOTE section in the SQLHOSTS file and adding information about the remote database.

For more information on the SQLHOSTS file, see *Editing the SQLHOSTS File* on page 15.

Access to remote databases is provided by using either DECNET or TCP/IP to establish a client/server connection to the remote machine.

Each entry in the REMOTE section can contain up to five fields, separated by spaces and/or tab characters.

The fields in the REMOTE section specify the following:

Field	Explanation
DATABASE	The DATABASE field specifies the name of the remote database.
NODE	The NODE field specifies the network node name of the remote machine. If you are using the TCP/IP interface, you can specify the IP address here.
PROTOCOL	You can specify DECNET or TCP depending on the type of network protocol to be used to create the client/server connection. The default, specified by '' (two single quote characters), is TCP.
INTERFACE	For TCP/IP, this field specifies whether IPv4 or IPv6 should be used. Specify 4 for IPv4 only Specify 6 for IPv6 only Enter an empty string with '' (two quotes) to use either IPv4 or IPv6 as indicated by the Node name lookup.

Field	Explanation
SERVICE	<p>TCP/IP If using the TCP/IP protocol, enter the TCP/IP port number the database server uses. The default is 1360.</p> <p>DECNET If using DECNET, enter the database name. The server listens to the network object using the same name as the database. (An old Mimer SQL version 7 database server using DECNET listens to the network object named "MIMER").</p>

Adding a Remote Database

To add a remote database:

- 1 Open the SQLHOSTS file in a text editor and locate the REMOTE section.
- 2 Fill in the fields, as specified above, according to your network configuration.

Example of a REMOTE Entry

```
REMOTE:
--
-- Database      Node          Protocol Interface Service
-- -----
REMTEST        STARTREK      TCP          ''        1360
```

Mimer SQL System Settings

You can edit your startup and shutdown files to automatically start and stop database servers at system startup and shutdown.

Automatic Database Server Start

If you want the Mimer SQL database server to start automatically whenever the system is booted, you must edit the `SYS$MANAGER:SYSTARTUP_VMS.COM` file.

The following example starts two Mimer SQL database servers:

```
$ MIMCONTROL/START TESTDB
$ MIMCONTROL/START INVENTORY
```

Automatic Database Server Shutdown

If you want to perform a controlled shutdown of the database server whenever the OpenVMS system is shut down, you must edit the `SYS$MANAGER:SYSHUTDOWN.COM` file and add the relevant commands at the end.

The following example stops two database servers:

```
$ MIMCONTROL/STOP TESTDB
$ MIMCONTROL/STOP INVENTORY
```

Removing a Mimer SQL Database

To remove a database, perform the following steps:

- 1** Check that no one is using the database.
- 2** Check that no database server is started against the database you are going to remove.
- 3** Create a list of all databank files by doing the following:

```
$ BSQL/SINGLE database
Username: SYSADM
Password: xxxxxx
SQL> SELECT DATABANK_FILENAME FROM SYSTEM.DATABANKS;
SQL> EXIT;
```
- 4** Using the list generated in the previous step, locate and delete all the physical databank files. If the file name does not contain a directory specification, the directory will be the home directory of the database.
- 5** Delete any directories that have been specifically created to hold databank files for the database.
- 6** Delete the database entry in:

```
SYS$SPECIFIC:[SYSMGR]SQLHOSTS.DAT
```


Chapter 4

Managing a Database Server

This chapter contains a short guide to administrating database servers under OpenVMS. It also describes how to use the MIMCONTROL command under OpenVMS.

For general information on managing database servers, refer to the *Mimer SQL System Management Handbook*.

The MIMCONTROL Command

Before you can access a database, the Mimer SQL database server must be started on the node it resides on.

You start, stop and control database servers on OpenVMS using the MIMCONTROL command.

Note: You cannot start the MIMCONTROL program by using the DCL command RUN.

Required Privileges

To use MIMCONTROL you must have either:

- SETPRV privilege

or

- CMKRLN, CMEXEC, SHMEM, SYSPRV, WORLD, TMPMBX, OPER, NETMBX, PSWAPM, DETACH, ALTPRI, PRMGBL, SYSGBL, SYSLCK and SYSNAM privileges.

If the resident memory feature is used (the `BPRresident` parameter in `MULTIDEFS.DAT` is set), you must have the `VMS$MEM_RESIDENT_USER` process right.

Database Server Parameters – the MULTIDEFS File

When you start a database server on an OpenVMS machine for the first time, MIMCONTROL will create a MULTIDEFS file containing parameter default values for the database server. These parameter values are based on the amount of memory installed on the machine.

You may also generate the MULTIDEFS file manually by using the MIMCONTROL/GENERATE command. For example:

```
$ MIMCONTROL/GENERATE TESTDB
```

It is not possible to change the parameters for a running database server.

You can fine-tune database server performance by adjusting the parameters as required.

Refer to the *Mimer SQL System Management Handbook* for details.

MIMCONTROL Syntax

You run the MIMCONTROL program is using arguments specified on the command-line.

For example:

```
$ MIMCONTROL/START TESTDB
```

Starts the database server and provides access to TESTDB.

If you run the MIMCONTROL command without any options it displays help on command-line arguments.

MIMCONTROL Command-line Arguments

For more information on MIMCONTROL arguments and their combinations, see the *Mimer SQL System Management Handbook*.

Argument	Function
/STATUS/DCL	Output status information about the specified database server into the symbol MIMER_STATUS for use in a command procedure. For details about the output string resulting from this option, see <i>MIMCONTROL (/STATUS/DCL)</i> on page 25.
/STATUS	Output status information about the specified database server.
/DISABLE	Disable new user connections to the database server. Users already connected are not affected.
/ENABLE	Enable new user connections to the database server.
/KILL	Kill the database server immediately. This should only be used in emergency situations when a normal stop does not work. The next time the database is started, all databanks that were open at the time the server was killed will be automatically checked. Connected users will receive an error the next time they attempt to access the database.
/LOGOUT=chan	Force logout of the specified channel number. Use channel numbers displayed by the USERS option of the MIMINFO command, see the <i>Mimer SQL System Management Guide</i> .

Argument	Function
/START [=timeout]	Start the database server. If the server does not become operational within the specified number of seconds, the server will be killed. (The default timeout is 600 seconds.)
/HOLD	This switch can only be used together with the /START switch. After the server has been started, the MIMCONTROL command will not return to the DCL prompt, but will wait for the server to stop. This can simplify writing scripts that automatically restart database servers. The termination status from the MIMCONTROL command will be the final status code from the database server process.
/STOP [=timeout]	Stop a database server. Any remaining users will be logged out. If the database server does not stop within the specified number of seconds, the server will be killed. (The default timeout is 120 seconds.)
/WAIT [=timeout]	Wait for all connected users to log out. If there are still users connected after the timeout period expires, the command fails. The timeout period should be given in seconds. If no timeout period is specified wait will be performed without any timeout.
/DUMP	Create a dump directory and produce dumps of all internal database server areas to files in that directory. The files produced can be examined by using MIMINFO, see the <i>Mimer SQL System Management Guide</i> .
/GENERATE	Create a new MULTIDEFS.DAT file with default for parameters, if the file is missing.
database	Specifies the name of the database to access. If a database name is not specified, the default database will be controlled. The default database is determined by setting the MIMER_DATABASE logical name. The DEFAULT setting in SQLHOSTS is not used for MIMCONTROL.

MIMCONTROL (/STATUS/DCL)

The MIMCONTROL/STATUS/DCL command is a special form of the MIMCONTROL/STATUS command which returns the database server status information in the form of a single string containing a comma-separated list which is useful when writing command procedures.

On OpenVMS, the MIMCONTROL command is silent and sets the DCL symbol MIMER_STATUS to the value of the status string.

You can use the lexical function `F$ELEMENT()` to extract the list elements. For example:

```
$ MIMCONTROL/STATUS/DCL
$ SHOW SYMBOL MIMER_STATUS
MIMER_STATUS == "Running,Enabled,LOKE_0:[PER.LOKE],0,A2,2025-01-06
16:10,121323127"
$ DIR=F$ELEMENT(2,"",MIMER_STATUS)
$ USERS=F$ELEMENT(3,"",MIMER_STATUS)
$ PID=F$ELEMENT(4,"",MIMER_STATUS)
$ SHOW SYMBOL DIR
DIR = "LOKE_0:[PER.LOKE]"
$ SHOW SYMBOL USERS
USERS = "0"
$ SHOW SYMBOL PID
PID = "A2"
```

The MIMPERF Command

The database server maintains a number of performance related counters counting events such as transactions, disk I/O, buffer pool accesses, client/server accesses and much more. The `MIMPERF` command can be used to monitor these counters.

`MIMPERF` can access remote databases running under any type of host. It can display statistics from Mimer database servers from version 9 and up.

VSI has a tool named T4 that continually collects performance counters from the VMS host system. The collected data is stored in simple CSV (Comma Separated Values) files. These files can be analyzed by tools such as TLViz or Excel. The `MIMPERF` tool has an option to generate CSV files so that the Mimer server data can be used together with other data collected by T4.

For more information about T4, please see the VSI web site:

<https://vmssoftware.com/products/t4/>

For more information on how to use `MIMPERF` with T4, please read

`MIMER$DOC:MIMPERF_T4.TXT`.

MIMPERF Syntax

```
$ MIMPERF [options] database
```

The options can be given either in VMS style (preceded by a `/`) or in UNIX style, depending on how the Mimer SETUP command was executed. Please note that UNIX style options in uppercase should be enclosed in double quotes on VMS.

Most counters are displayed as the number of events that happened per second. If this number is greater than zero but less than one, it may be displayed as `"0."` (a zero followed by a decimal point) to distinguish it from zero (meaning that no such events happened).

MIMPERF Command-line Arguments

VMS style	Unix style	Description
<code>/SYSTEM</code>	<code>--system</code> <code>-S</code>	Display general database server counters interactively
<code>/TRANSACTION</code>	<code>--transaction</code> <code>-T</code>	Display counters detailing transaction rates

VMS style	Unix style	Description
/COMMUNICATION	--communication -C	Display counters from the communication between the database server and connected clients
/POOL	--pool -P	Show the buffer pool usage and hit rates
/COMPILER	--compiler -Q	Show how the compilers for SQL statements and PSM procedures are used
/SPACE	--space -A	Show the space usage in the SQL pool
/EXPLAIN	--explain -x	Use this switch together with any of the switches above to display a short explanation of the counters
/T4=file	--t4=file -4 file	Collect all Mimer counters to a T4 compatible CSV file
/INTERVAL=n	--interval=n -i n	Set the sample interval to n seconds. The default is 10 seconds for the interactive displays and 60 seconds for T4.
/ENDING=" [YYYY-MM-DD]HH:MM[:SS]"	--ending=t -e t	Stop collection at the specified time. Note that there should be a space between the (optional) date and the time. If a space is included, the value must be enclosed in double quotes.

The MIMTCP Server

If you are using the TCP/IP protocol, a MIMTCP server listening to a specific port (usually port 1360) will be started the first time the database server is started.

TCP/IP Port Number

The TCP/IP port number that the MIMTCP server will listen to is specified in the **TCPPort** parameter in the **MULTIDEFS.DAT** file. If several database servers specify the same port number, they will share the same MIMTCP server.

When a client connects to the TCP/IP port, the MIMTCP server will accept the connection. The client specifies the database to which a connection is to be established and the MIMTCP server will hand over the connection to the appropriate database server. All further communication between the client and the database server is then done directly without involving the MIMTCP server.

Note that if you specify a `TCPPort` parameter with a preceding + sign (like `+1377`), the database server will listen directly on the specified port. A MIMTCP server will not be started for that port. Clients connecting to the port will reach the database server directly, avoiding the overhead of going through the MIMTCP server. However, such port number can not be shared between database servers.

A server that listens on its own port will still accept connections from MIMTCP servers listening on other ports.

System Logical Names

Whenever a MIMTCP server starts, it will define the system logical name `"MIMTCP_xxxx"` (where `xxxx` is the port number) to be the PID of the MIMTCP server process. This makes it easy to find the MIMTCP server process that is listening to a particular TCP/IP port.

MIMTCP log file

The MIMTCP server will log startup and error messages in the log file `SYS$MANAGER:MIMTCP_xxxx.LOG`, where `xxxx` is the port number that the MIMTCP server listens to.

Controlling MIMTCP servers

The command procedure `MIMER$EXE:TCPCONTROL.COM` can be used to manage MIMTCP processes. The first parameter given to the procedure controls what the procedure should do. If no parameter is given, a short help message is displayed. The following example shows how the MIMTCP server for port 1360 is stopped and a new server for port 1337 is started:

```
$ @MIMER$EXE:tcpcontrol
Usage: TCPCONTROL STATUS          ! Display status for all MIMTCP processes
      TCPCONTROL START  [port] ! Start MIMTCP process for a port
      TCPCONTROL STOP   [port] ! Stop the MIMTCP process for a port
      TCPCONTROL STOP  ALL    ! Stop all running MIMTCP processes
$ @MIMER$EXE:tcpcontrol status
      Pid      Port Version      Username      Started
      00000227    1360 1109E      SYSTEM      15-JAN-2025 22:14:29.22
$ @MIMER$EXE:tcpcontrol stop 1360
MIMTCP process for port 1360 STOPPED
$ @MIMER$EXE:tcpcontrol start 1337
Starting MIMTCP process version 1109E
%RUN-S-PROC_ID, identification of created process is 00004D04
$ @MIMER$EXE:tcpcontrol status
      Pid      Port Version      Username      Started
      00004D04    1337 1109E      SYSTEM      15-JAN-2025 23:09:11.96
```

Starting and stopping MIMTCP servers explicitly using the `TCPCONTROL` procedure is rarely needed. When the `MIMCONTROL/START` command is used, a MIMTCP process will be started automatically. This process will normally be active until the machine is shut down. Since the MIMTCP process does not hold any resources, it is not necessary to shut it down explicitly in the machine shutdown procedure.

Using a Memory Resident Buffer Pool

The buffer pool can be created in two different ways. If the MULTIDEFS.DAT parameter **BPRresident** is left blank (the default) the buffer pool is allocated in normal process memory and is backed by the paging file. This means that the buffer pool is subject to normal virtual memory paging; if the system memory requirements increases the operating system may page out parts of the buffer pool.

Since the paging file is used as backing store the paging file quota of the database server process is increased to a suitable value. The working set quotas are also increased. These quotas are ultimately limited by the system parameter **WSMAX**, so when a large buffer pool is created with this method the **WSMAX** parameter must be increased accordingly.

At database server startup, the **WSMAX** parameter is checked. If it is insufficient an error message is displayed with the required value.

If the **BPRresident** parameter specifies a name, the buffer pool is allocated as a memory resident area, i.e. physical memory in the machine is reserved. This has several advantages:

- Since physical memory is used, the buffer pool contents are always available and is never swapped out.
- The paging files are not used for the buffer pool; they do not need to be extended.
- The buffer pool does not use working set quota for the server process.
- The buffer pool uses a larger virtual page size which makes memory accesses more efficient.

The name that **BPRresident** specifies will be used to name the memory resident global section. Please note that it is case sensitive. The name must be unique (the same section can not be used by two different database servers).

The user that starts a server using a resident memory area must have the process right **VMS\$MEM_RESIDENT_USER**. This can be granted to a user by using **AUTHORIZE**:

```
$ SET DEF SYS$SYSTEM
$ MCR AUTHORIZE
UAF> GRANT/IDENTIFIER VMS$MEM_RESIDENT_USER SMITH
%UAF-I-GRANTMSG, identifier VMS$MEM_RESIDENT_USER granted to SMITH
UAF> EXIT
```

To create a reserved memory area, first calculate how big it should be by configuring a buffer pool in the MULTIDEFS.DAT file. Use the command **MIMCONTROL/STATUS** to calculate the size in MB for the bufferpool. (You can use the command while the server is stopped.)

```
$ mimcontrol/status targetdb
The server for database TARGETDB is Stopped
Directory for SYSDB is dka1:[targetdb]
Buffer pool size: 9207 MiB
```

It is recommended that the reserved memory is created with the **/ALLOCATE** qualifier, which ensures that huge pages are used and that memory is reserved when the system is booted. It is also recommended that the **/PAGE_TABLES** qualifier is specified so that space for the page tables is also reserved. Also specify **/ZERO** to have the pages initiated to zero when the system is booted.

```
$ mcr sysman
SYSMAN> reserved_memory add targetdb/size=9207/allocate/page_tables/zero
```

After a reserved memory has been added you should run AUTOGEN with feedback to reconfigure system parameters and reboot your system.

```
$ @SYS$UPDATE: AUTOGEN SAVPARAMS TESTFILES
$ @SYS$UPDATE: AUTOGEN GENPARAMS SETPARAMS FEEDBACK
```

More information about reserved memory is found in System Managers Manual volume 2, chapter 3.11:

https://docs.vmssoftware.com/vsi-openvms-system-manager-s-manual-volume-2-tuning-monitoring-and-complex-systems/#RESERV_MEMORY

How to use AUTOGEN is described in chapter 1 of the same manual.

Determining Buffer Pool Size

The buffer pool size is calculated by the MIMCONTROL/STATUS command. This command reads the parameter configuration in the MULTIDEFS.DAT file and calculates the required buffer pool size. The size is displayed in KBytes or MBytes and is rounded upwards so the value can be used for a resident memory reservation.

To see the exact buffer pool size, use the MIMCONTROL/STATUS/DCL command. The last value returned in the MIMER_STATUS symbol is the buffer pool size in bytes.

Process Quotas for the Database Server

When MIMCONTROL/START is used to start a database server process quotas are calculated according to the MULTIDEFS.DAT parameter file.

The size of the database server is calculated. The size includes communication areas (70K per User as specified in MULTIDEFS.DAT), thread stacks, local data, initial SQL Pool (SQLPool parameter) and code. If BPResident is not specified, the buffer pool size is also included.

The WSDEFAULT and WSQUOTA (working set quotas) of the server process is set to the calculated server size.

The PGFLQUOTA (page file quota) is set to the calculated server size plus the size the SQL pool can grow to according to the MULTIDEFS.DAT parameter MaxSQLPool. This means that the MaxSQLPool parameter can be used to control the paging file quota for the process.

The WSEXTENT quota is set to the WSMAX system parameter.

Troubleshooting Tips

In order to successfully start a database server, the following conditions must be fulfilled:

- The system databank file, SYSDB110.dbf, must have been created. See *Generating System Databanks and SYSADM* on page 17
- There must be an entry for the database in the local section of the SQLHOSTS file. See *Editing the SQLHOSTS File* on page 15
- The ProcName of the MULTIDEFS file must not specify a process name prefix that is identical to that of another running multi-user system.
- There must not be any other node in a cluster which has started the same database server.

- The database must not be in use in single-user access mode at the time the database server is started.
- The file `SYS$MANAGER:MIMERKEY_IA64.DAT` (or `MIMERKEY_X86_64.DAT`) must contain a valid Mimer SQL license key.

Chapter 5

Running Mimer BSQL Scripts

This chapter describes how to run BSQL scripts in the Mimer SQL environment.

Running a BSQL Script

BSQL can be used to run SQL commands from within a script. There are several ways to use BSQL and some examples are given here.

You can use the READ command from within BSQL to read a file containing SQL statements:

```
$ CREATE Q.SQL
SELECT 1+1 FROM SYSTEM.ONEROW;
$ BSQL/USER=SYSADM/PASSW=SYSADM
READ 'Q.SQL';
```

To use BSQL from within a command procedure (.COM file), you do like this:

```
$ BSQL
SYSADM
SYSADM
SELECT 1+1 FROM SYSTEM.ONEROW;
$ ! next DCL command beginning with dollar ends program input.
```

To execute a single SQL command, the /QUERY switch can be used with BSQL:

```
$ BSQL/USER=SYSADM/PASSW=SYSADM/QUERY="SELECT 1+1 FROM SYSTEM.ONEROW"
```

The VMS command PIPE can be used to create Unix-like pipes with Unix-like redirection. This command reads SQL statements from the file Q.SQL:

```
$ PIPE BSQL/USER=SYSADM/PASSW=SYSADM < Q.SQL > RESULT.TXT
```

Old-time VMS users would achieve the same thing by redefining SYS\$INPUT and SYS\$OUTPUT. By defining them in USER mode, the definitions are dropped automatically at image (program) exit:

```
$ DEFINE/USER SYSS$INPUT Q.SQL
$ DEFINE/USER SYSS$OUTPUT RESULT.TXT
$ BSQL/USER=SYSADM/PASSW=SYSADM
```

A problem with all the examples above is that the password for the Mimer ident used is stored in a file. This should generally be avoided unless the security of the file can be guaranteed.

The problem can be solved by adding an OS_USER login to the user. A user with an OS_USER login can log in without providing a password. (This does not work over TCP/IP.)

Example - same username for VMS and Mimer:

```
$ BSQL /USER=SYSADM /PASSW="SYSADMPASSW"  
SQL> CREATE IDENT PER AS USER;  
SQL> ALTER IDENT PER ADD OS_USER 'PER';  
SQL> EXIT;
```

Now VMS user PER can do:

```
$ BSQL /USER="" /QUERY="SELECT 1+1 FROM SYSTEM.ONEROW"
```

Example - different usernames for VMS and Mimer:

```
$ BSQL /USER=SYSADM /PASSW="SYSADMPASSW"  
SQL> CREATE IDENT DANIEL AS USER;  
SQL> ALTER IDENT DANIEL ADD OS_USER 'DAN';  
SQL> EXIT;
```

Now VMS user DAN can connect as Mimer user DANIEL with:

```
$ BSQL /USER="DANIEL" /PASSW=""
```

Chapter 6

Building Mimer Applications on OpenVMS

There are three native API's provided in the Mimer distribution. Each API has a shared library and an options file (.OPT) for linking. There is also a logical name for each shared library, defined by the `SYS$MANAGER:MIMER$SETUP_xxxxx.COM` procedure:

Logical name	Points to	Used by
MIMER\$API	SYSShare:MIMER\$API_xxxxx	MIMER\$LIB:MIMER\$API.OPT
MIMER\$ODBC	SYSShare:MIMER\$ODBC_xxxxx	MIMER\$LIB:MIMER\$ODBC.OPT
MIMER\$SQL	SYSShare:MIMER\$SQL_xxxxx	MIMER\$LIB:MIMER\$SQL.OPT

The options file directs the linker to use the logical name to find the shareable image. For example, `MIMER$LIB:MIMER$SQL.OPT` contains:

```
MIMER$SQL/SHARE
```

If you link your application with this options file, the resulting program will contain a reference to the shared library named `MIMER$SQL` (without a version suffix), as shown by the following example:

```
$ LINK EXAMPLE,MIMER$LIB:MIMER$SQL/OPT
$ ANALYZE/IMAGE/OUT=X.TMP EXAMPLE
$ SEA X.TMP "SHAREABLE IMAGE LIST" /WIN=(0,10)
  Shareable Image List
    MIMER$SQL
      (LESS/EQUAL, 11., 1105.)
    DECC$SHR
      LESS/EQUAL, 1., 1.)
```

If you try to run this program without a definition of the logical name `MIMER$SQL`, the shareable image will not be found.

```
$ RUN EXAMPLE
%DCL-W-ACTIMAGE, error activating image MIMER$SQL
-CLI-E-IMAGEFNF, image file not found
SIV$DKA100:[SYS0.SYSCOMMON.][SYSLIB]MIMER$SQL.EXE;
```

Use `SYS$MANAGER:MIMER$SETUP_xxxxx.COM` to select the Mimer version to use, which defines the required logical names.

```
$ @SYS$MANAGER:MIMER$SETUP_1109E
$ SHOW LOG MIMER$SQL
  "MIMER$SQL" = "SYS$SHARE:MIMER$SQL_1109E.EXE" (LNM$PROCESS_TABLE)
$ RUN EXAMPLE
INFORMATION_SCHEMA ASSERTIONS VIEW
INFORMATION_SCHEMA ATTRIBUTES VIEW
INFORMATION_SCHEMA CHARACTER_SETS VIEW
INFORMATION_SCHEMA CHECK_CONSTRAINTS VIEW
...
```

Since `EXAMPLE.EXE` is linked to a logical name, the `SYS$MANAGER:MIMER$SETUP_xxxxx.COM` procedure will set the version of the Mimer libraries the program uses, without having to re-link.

Building example programs

The directory `MIMER$EXAMPLES` contains numerous example programs you can build on OpenVMS. Please read the supplied `.TXT` files for more information.

```
$ DIR MIMER$EXAMPLES:*.TXT
Directory SYS$COMMON:[MIMER1109E.EXAMPLES]
README_ESQL.TXT;1    README_MIMERAPI.TXT;1          README_MSQ.L.TEXT;1
```

Chapter 7

Using the JDBC Driver

The Mimer SQL distribution includes a JDBC driver. This driver enables Java programs running on OpenVMS to access a Mimer SQL database server.

The JDBC driver is a ‘type 4’ driver which means that it is written entirely in Java, and can be moved to any platform supporting Java.

The driver, MIMJDBC3.JAR, supports the JDBC 3 standard, and is for Java 1.4 or later.

For more information about Java and JDBC, please see:

- `SYS$COMMON: [JAVA* .DOCS] INDEX .HTML` – Java information for more recent versions
- `MIMER$DOC:MIMJDBEN .PDF` – Information on the Mimer JDBC driver.
- <https://www.oracle.com/technetwork/java/javase/jdbc/index.html> – JDBC technology information.

Using the JDBC Driver

To use the JDBC driver, you must first set up the OpenVMS Java environment.

Defining Java Commands

Use the following command to define the Java commands (Java version 1.4.2 is used in the example):

```
$ @SYSS$MANAGER:JAVA$142_SETUP
```

Setting CLASSPATH

To use a Mimer JDBC driver, the Java environment must be able to find it.

The logical name CLASSPATH is used for this purpose. This logical name contains a list of directories and Java archives (.ZIP and .JAR files).

On OpenVMS you can use either the JAVA\$CLASSPATH or CLASSPATH logical name to specify a Java classpath. The JAVA\$CLASSPATH logical name is easier to use since it uses standard OpenVMS file specifications.

Example

```
$ DEFINE JAVA$CLASSPATH MIMER$LIB:MIMJDBC3.JAR, SYS$DISK:[]
```

It is also possible to use the CLASSPATH logical name. This logical name uses a Unix syntax to specify a search path. Please read the OpenVMS Java documentation for details.

The following example sets the CLASSPATH logical name to include the Mimer JDBC 1 driver.

Since the equivalence string becomes rather long, and must be enclosed in quotes, a DCL string is constructed.

Example

```
$ SHOW LOG CLASSPATH
"CLASSPATH" = "/sys$common/java/lib/JDK118_CLASSES.ZIP:."
(LNM$PROCESS_TABLE)
$ CLASSPATH=F$TRNLNM("CLASSPATH")+":/MIMER$LIB/MIMJDBC3.JAR"
$ DEFINE CLASSPATH '''CLASSPATH'''
```

The Mimer JDBC driver should now be accessible.

Note: Using logical names that enclose directory specifications with < and > is problematic in Java. Please make sure you use [and] instead.

Verifying the Environment

Since the driver contains a `main()` function, it is possible to execute it as a program for testing purposes.

Use the `-version` switch to verify that the Java environment can locate and use the Mimer JDBC driver. Note that quotes must be used since Java package names are case sensitive.

```
$ JAVA "com.mimer.jdbc.Driver" -version
Mimer JDBC driver version 3.31 (12385)
```

Testing the Connection

Use the `-ping` switch to test that the driver can make a connection with a Mimer SQL v10.1 database server.

Please read the JDBC driver guide for an explanation of the syntax of the connection URL.

```
$ java "com.mimer.jdbc.Driver" -ping
"jdbc:mimer:local://SYSADM:SYSADM@/targetdb"
Database connection established.
getDatabaseProductName():      Mimer SQL Experience
getDatabaseProductVersion(): 11.00.0000 Mimer SQL Experience 11.0.0a

Ping tests:
  0      0 ms
  1      0 ms
  2      1 ms
  3      0 ms
  4      0 ms
  5      1 ms
  6      0 ms
  7      0 ms
  8      0 ms
  9      0 ms
avg      0 ms      min      0 ms      max      1 ms
```

Finally, compile and execute the JDBC example program. You should copy the example program to a private directory and edit it in order to set the connection URL string, database user name and passwords.

```
$ SET DEF [SOMEWHERE.PRIVATE]
$ COPY MIMER$EXAMPLES:EXAMPLE.JAVA []
$ ! Edit the example. Alter the URL and username/password
$ EDIT EXAMPLE.JAVA
$ JAVAC EXAMPLE.JAVA
$ JAVA "Example"
```


Appendix A

Distributed Files

When installing Mimer SQL with the `PRODUCT INSTALL` command, a new directory named `[MIMERxxxx]` is created under `SYS$COMMON:`, where `xxxx` is the version number of the product. A few files are placed outside the Mimer directory in system directories.

Files in System Directories

The names of files placed in system directories are suffixed with `_xxxx`, where `xxxx` is the version number of the Mimer product.

File Name	Description
<code>SYS\$MANAGER:MIMER\$SETUP_xxxxx.COM</code>	Command procedure that defines logical names and commands so a process can use this version of Mimer.
<code>SYS\$SHARE:MIMCOMM_xxxxx.EXE</code>	Image for fast Mimer access in 32-bit Java
<code>SYS\$SHARE:MIMCOMM64_xxxxx.EXE</code>	Image for fast Mimer access in 64-bit Java
<code>SYS\$SHARE:MIMER\$DBP_xxxxx.EXE</code>	Protected image for shared memory communication
<code>SYS\$SHARE:MIMER\$DBS_xxxxx.EXE</code>	Executable code for single-user access
<code>SYS\$SHARE:MIMER\$API_xxxxx.EXE</code>	Shareable image with the Mimer SQL C API
<code>SYS\$SHARE:MIMER\$ODBC_xxxxx.EXE</code>	Image containing the ODBC interface
<code>SYS\$SHARE:MIMER\$SQL_xxxxx.EXE</code>	Image containing the API for Embedded SQL
<code>SYS\$STARTUP:MIMER\$SHUTDOWN_xxxxx.COM</code>	Command procedure that deinstalls shareable images. Should be called from <code>SYS\$MANAGER:SYSHUTDWN.COM</code>
<code>SYS\$STARTUP:MIMER\$STARTUP_xxxxx.COM</code>	Command procedure that installs shareable images. Should be called from <code>SYS\$MANAGER:SYSTARTUP_VMS.COM</code>
<code>SYS\$SYSROOT:[000000]MIMERxxxx.DIR</code>	Directory tree with files for this specific version of Mimer SQL

Files in the Mimer Root Directory

File Name	Description
VERSION.DAT	Contains the version number of the Mimer SQL distribution.

Documentation Files (MIMER\$DOC)

File Name	Description
DTOA_LICENSE.TXT	License text for the DTOA library used by Mimer SQL,
MIMER_LICENSE.TXT	License text for Mimer SQL
MIMJDBEN.PDF	JDBC usage guide.
MIMPERF_T4.TXT	Describes how to add Mimer SQL performance metrics to the T4 tool.
MIMSQLEN.PDF	The Mimer SQL documentation.
MIMVMS.PDF	The VMS guide.
RELNOTEN.PDF	Mimer SQL Release Notes.

Example Files (MIMER\$EXAMPLES)

File Name	Description
BLOBSAMP.EC	Example of a program written in embedded C that stores and retrieves binary data.
BLOBSAMP.MSQ BLOBSAMP_PRG.C	A Module SQL example that stores and retrieves binary data.
COMINGSOON.EC	Example program in embedded C that calls a PSM procedure.
COMINGSOON.MSQ COMINGSOON_PRG.C	A Module SQL program that calls a PSM procedure.
DEFAULTKEY.MCFG	Mimer license for up to ten simultaneous users. For testing purposes.
DSQL_CALLER.C DSQL_MODULE.MSQ	A Module SQL program using dynamic SQL.
DSQL.EC	Embedded C examples that demonstrates the use of dynamic SQL.
DSQL.H	Header file for the dynamic SQL example.
DSQLSAMP.C	Main program for the dynamic SQL example.
DYNCALL.EC	Example program in embedded C that demonstrates a dynamic query.
EXAMPLE.EC	Very simple embedded C example.
EXAMPLE.ECO	Very simple embedded COBOL example.
EXAMPLE.EFO	Very simple embedded FORTRAN example.
Example.java	Java example program using JDBC.
EXAMPLE.MSQ EXAMPLE_PRG.C EXAMPLE_PRG.COB EXAMPLE_PRG.FOR EXAMPLE_PRG.PAS	Simple Module SQL example with code in various languages calling the procedure.
EXDAT.SQL	A BSQL script that populates an example database.
EXDEF.SQL	A BSQL script that creates example users, tables and procedures.
MIMERAPIEX1.C	Simple Mimer SQL C API test program.
MIMERAPIEX2.C	Simple Mimer SQL C API test program.
MIMERAPIEX3.C	Simple Mimer SQL C API test program.
MULTILANG.EC	An embedded C program coded in UTF-8 having a table name using Unicode characters.
OSQL.C	An ODBC example
SIMPLE.EC	Simple embedded SQL program in C.

File Name	Description
SIMPLE.ECO	Simple embedded SQL program in COBOL.
SIMPLE.EFO	Simple embedded SQL program in FORTRAN.
SIMPLE.MSQ SIMPLE_PRG.C SIMPLE_PRG.COB SIMPLE_PRG.FOR SIMPLE_PRG.PAS	A simple Module SQL example with code calling the procedures from C, COBOL, FORTRAN and PASCAL.
SINGLEDEFS.DAT	Contains a template for database parameters in single-user mode, see the <i>Mimer SQL System Management Handbook</i> .
SQLHOSTS.DAT	Contains a template for the SQLHOSTS.DAT file. The actual SQLHOSTS file is pointed to by the MIMER_SQLHOSTS logical name (normally SYS\$MANAGER:SQLHOSTS.DAT). Do not edit this template file.
T4\$MIM_MON.COM	Command procedure that helps with integrating Mimer SQL with the T4 tool. See MIMER\$DOC:MIMPERF_T4.TXT for more information

Executable Programs (MIMER\$EXE)

File Name	Description
BSQL.EXE	Program that executes SQL statements which are entered interactively or read from a command file. It is described in the <i>Mimer SQL User's Manual</i> .
DBANALYZER.EXE	Program that analyzes a database schema and provides suggestions for optimizations.
DBC.EXE	Program that can check if a databank file is internally consistent. It is described in the <i>Mimer SQL System Management Handbook</i> .
DBOPEN.EXE	Program that opens and restarts all databanks in a database. It is described in the <i>Mimer SQL System Management Handbook</i> .
ESQL.EXE	Pre-processor for embedded SQL.
EXLOAD.EXE	Program to load the example database.
MIMCONTROL.EXE	The MIMCONTROL command, which is used to control database servers, <i>The MIMCONTROL Command</i> on page 23.
MIMER\$SETUP_CLEAR.COM	Procedure to remove logical names, commands and symbols pointing to this version.

File Name	Description
MIMEXPER.EXE	The Mimer SQL Experience database server. Do not start this program directly. Use MIMCONTROL to start a database server and specify which type of server to start by setting the parameter ServerType in the MULTIDEFS.DAT file.
MIMINFO.EXE	Program that can display status information for a database server.
MIMINM.EXE	The Mimer SQL InMemory database server. Do not start this program directly. Use MIMCONTROL to start a database server and specify which type of server to start by setting the parameter ServerType in the MULTIDEFS.DAT file.
MIMLICENSE.EXE	Application used to administrate the license key(s).
MIMLOAD.EXE	Utility to load and unload data.
MIMPERF.EXE	A program to display server performance counters.
MIMREPADM.EXE	Administration utility for Mimer Replication.
MIMSYNC.EXE	Utility to bring two replicated Mimer systems back into sync.
MIMTCP.EXE	The program executed by the MIMTCP server, see <i>The MIMTCP Server</i> on page 27. Do not start this program directly.
MSQL.EXE	A preprocessor for Module SQL. Described in the <i>Module SQL</i> chapter of the <i>Mimer SQL Programmer's Manual</i> .
REPSERVER.EXE	Mimer Replication server.
SDBGEN.EXE	Program used to create the initial Mimer SQL system databank files in a database, described in the <i>Mimer SQL System Management Handbook</i> .
SQLMONITOR.EXE	SQL Monitor tool. Described in the <i>Mimer SQL System Management Handbook</i> .
SQLTRANSLATOR.EXE	Tool that can translate SQL statements in programs or scripts from a non-compatible SQL syntax to valid Mimer SQL syntax. It is described in the <i>Mimer SQL System Management Handbook</i> .
TCPCONTROL.COM	Procedure to manage MIMTCP processes.

Library Files (MIMER\$LIB)

File Name	Description
MIMER.CLD	Command definitions for all the executable programs supplied with the Mimer SQL software.
MIMER.HLB	HELP library for Mimer.
MIMER\$API.OPT	Options file used for linking Mimer SQL C API applications.
MIMER\$ODBC.OPT	Options file used for linking ODBC applications.
MIMER\$SQL.OPT	Options file used for linking Mimer SQL embedded applications.
MIMERAPI.H	Header file for Mimer SQL C API programs.
MIMERRORS.H	Header file for Mimer SQL C API programs.
MIMJDBC3.JAR	JDBC 3 driver.
MIMODBC.H	C-definitions for Mimer ODBC specific descriptor attributes, working with 64-bit integers.

Appendix B

Using x86 Cross-Compiling Tools with Mimer

VMS Software Inc. (VSI) has released the product X86_TOOLS for Itanium. This product makes it possible to compile and build software for x86_64 using cross-compilers.

When using X86_TOOLS to link a Mimer application, you will need Mimer libraries compiled for x86_64 on Itanium. This is provided in the product MIMERX86LIB.

Installing MIMERX86LIB on Itanium

Download the installation file MIMERX86LIB-I64.ZIPEXE from the Mimer download site <https://developer.mimer.com/products/downloads/>.

The downloaded file is a self-extracting ZIP file. Just execute the file to extract the .PCSI files:

```
$ RUN MIMERX86LIB-I64.ZIPEXE
UnZipSFX 6.00 of 20 April 2009, by Info-ZIP (http://www.info-zip.org).
  inflating: MIMER-I64VMS-MIMERX86LIB-U1100-8A-1.PCSI$COMPRESSED
  inflating: mimer-i64vms-mimerx86lib-u1100-8a-1.pcsi$compressed_VNC
```

Then do PRODUCT INSTALL to install the product:

```
$ PRODUCT INSTALL MIMERX86LIB

Performing product kit validation of signed kits ...
%PCSI-I-VSIVALPASSED, validation of SIV$DKA300:[PER]MIMER-I64VMS-MIMERX86L
IB-U1100-8A-1.PCSI$COMPRESSED;1 succeeded

The following product has been selected:
    MIMER I64VMS MIMERX86LIB U11.0-8A           Layered Product

Do you want to continue? [YES]

Configuration phase starting ...

You will be asked to choose options, if any, for each selected product and for
any products that may be installed to satisfy software dependency
requirements.

Configuring MIMER I64VMS MIMERX86LIB U11.0-8A: Mimer SQL x86 Cross libraries
for IA64

Copyright © 2025 Mimer Information Technology AB. All rights reserved.

Produced by Mimer Information Technology AB

This product requires no license keys

* This product does not have any configuration options.

Execution phase starting ...

The following product will be installed to destination:
    MIMER I64VMS MIMERX86LIB U11.0-8A           DISK$I64SYS:[VMS$COMMON. ]

Portion done: 0%...20%...60%...90%...100%

The following product has been installed:
    MIMER I64VMS MIMERX86LIB U11.0-8A           Layered Product

MIMER I64VMS MIMERX86LIB U11.0-8A: Mimer SQL x86 Cross libraries for IA64

Insert the following lines in SYS$MANAGER:SYSTARTUP_VMS.COM:
    @SYS$STARTUP:MIMER$STARTUP_X86LIB
```

You should insert the command in the SYSTARTUP_VMS file as instructed. The command will define the system logical name MIMER\$X86LIB to point to the directory where the Mimer libraries for x86_64 can be found.

Distributed files

The following files can be found under MIMER\$X86LIB:

File Name	Description
MIMER\$API.EXE	Library for the MIMER C API
MIMER\$API.OPT	Options file used when linking applications using the MIMER C API
MIMER\$ODBC.EXE	Library for ODBC
MIMER\$ODBC.OPT	Options file used when linking ODBC applications

File Name	Description
MIMER\$SQL.EXE	Library for applications preprocessed by ESQL
MIMER\$SQL.OPT	Options file used when linking applications preprocessed by ESQL
VERSION.DAT	Version number for the libraries in the directory.

Using the cross-compiler tools with Mimer

When linking a native Mimer application, you link with an option file found under MIMER\$LIB. When using a cross-compiler, use the same commands, but link with an option file found under MIMER\$X86LIB instead.

An example:

```
$ @SYS$MANAGER:X86_XTOOLS$SYLOGIN.COM      ! Setup cross-compiler tools
$ @SYS$MANAGER:MIMER$SETUP_1109E            ! Use Mimer 1109E
$ CREATE/DIR [.TEST]                         ! Create a test directory
$ SET DEF [.TEST]
$ COPY MIMER$EXAMPLES:SIMPLE.EC []           ! Copy example program
$ ESQL/NOLOGO/C SIMPLE                      ! Preprocess it with ESQL
$ CC SIMPLE                                ! Compile it using cross-compiler
$ LINK SIMPLE,MIMER$X86LIB:MIMER$SQL/OPT    ! Link it with Mimer x86_64 library
```

Now the image SIMPLE.EXE can be executed on a machine that runs VMS on x86_64 and has Mimer SQL version 11.0.9E installed.

Index

A

API 5
applications
 running 33

B

BPRresident 29
BSQL 5
BSQL scripts 33

C

command-line arguments
 MIMCONTROL 24
 SDBGGEN 17
cross-compile 4

D

data source 5
databanks 5
 initial size 18
database 5
 accessing remote 19
 establishing 15
 overview 15
 remote 19
 adding 20
 removing 21
database server 1
 MULTIDEFS 23
 shutdown 20
 startup 20
 troubleshooting 30

DBANALYZER 3
DBC 3
DBOPEN 3
DCL 5
documentation
 conventions 4
 resources 4
Dynamic SQL 5

E

Embedded SQL 5
embedded SQL 1
ESQL 3, 5
EXLOAD 3

H

home directory 15

I

installing
 Mimer SQL 7
Itanium 4

J

Java 37
 CLASSPATH 37
 commands 37
 connection 38
 environment 38
JDBC 37
 driver 37
JDBC driver 2
 using 37

L

license
 default 1
 run-time 1
license key 9, 11

M

MIMCONTROL 3, 24
 (/STATUS/DCL) 25
 command-line arguments 24
 privileges 23
 syntax 24
Mimer ESQL 37
Mimer SQL 1, 7, 15, 23, 33, 35, 37,

41, 47
 removing 12
Mimer SQL C API 2
MimerPy 2
MIMERX86LIB 47
MIMINFO 3
MIMLICENSE 3, 11
 syntax 12
MIMLOAD 3
MIMPERF 3
mimperf 26
MIMREPADM 3
MIMSYNC 3
MIMTCP 27
 port number 27
Module SQL 2, 3
MSQL 2, 3
MULTIDEFS 23

O
ODBC 6
 ODBC driver 2
OpenVMS system requirements 4
OS_USER 34
overview
 establishing database 15

P
PEP 249 2
PRODUCT INSTALL 8
PSM 6
Python 2

R
REPSERVER 3
resident memory area 29

S
SDBGEN 3, 17
 command-line arguments 17
 generating system databanks 17
 syntax 17
 SYSADM 17
 SYSADM password 18
SQL 6
 Dynamic 5
 embedded 5
SQLHOSTS 6, 19
 DEFAULT 15
 editing 15
 LOCAL 15
 REMOTE 15
SQLMONITOR 3
SQLTRANSLATOR 3
SYSADM password 18
SYSDB 17
system databanks
 generating 18
 LOGDB 17
 SQLDB 17
 SYSDB 17
 TRANSDB 17
system settings 20

T
T4 3
Table 6
TCP/IP 27
TCPCONTROL 3
Troubleshooting 30

U
uninstall 12
Utilities 3

X
x86_64 4
X86_TOOLS 47