Wikipedia API Data Model

for use with Invantive SQL

24.0

invantive
the SQL company

Copyright

Important Safety and Usage Information

Intended Use and Limitations: This software, developed by Invantive, is designed to support a variety of business and information technology data processing functions, such as accounting, financial reporting an sales reporting. It is important to note that this software is not designed, tested, or approved for use in environments where malfunction or failure could lead to life-threatening situations or severe physical or environmental damage. This includes, but is not limited to:

- Nuclear facilities: The software should not be used for operations or functions related to the control, maintenance, or operation of nuclear facilities.
- Defense and Military Applications: This software is not suitable for use in defense-related applications, including but not limited to weaponry control, military strategy planning, or any other aspects of national defense.
- Aviation: The software is not intended for use in the operation, navigation, or communication systems of any aircraft or air traffic control environments.
- Healthcare and Medicine Production: This software should not be utilized for medical device operation, patient data analysis for critical health decisions, pharmaceutical production, or medical research where its failure or malfunction could impact patient health.
- Chemical and Hazardous Material Handling: This software is not intended for the management, control, or operational aspects of chemical plants or hazardous material handling facilities. Any malfunction in software used in these settings could result in dangerous chemical spills, explosions, or environmental disasters.
- Transportation and Traffic Control Systems: The software should not be used for the control, operation, or management of transportation systems, including railway signal controls, subway systems, or traffic light management. Malfunctions in such critical systems could lead to severe accidents and endanger public safety.
- Energy Grid and Utility Control Systems: This software is not designed for the control or operation of energy grid systems, including electrical substations, renewable energy control systems, or water utility control systems. The failure of software in these areas could lead to significant power outages, water supply disruptions, or other public utility failures, potentially endangering communities and causing extensive damage.
- Other High-Risk Environments: Any other critical infrastructure and environments where a failure of the software could result in significant harm to individuals or the environment.

User Responsibility: Users must ensure that they understand the intended use of the software and refrain from deploying it in any setting that falls outside of its designed purpose. It is the responsibility of the user to assess the suitability of the software for their intended application, especially in any scenarios that might pose a risk to life, health, or the environment.
Disclaimer of Liability: Invantive disclaims any responsibility for damage, injury, or legal consequences resulting from the use or misuse of this software in prohibited or unintended applications.

Contents

1 SQL Driver for Wikipedia API

Invantive SQL is the fastest, easiest and most reliable way to exchange data with the Wikipedia API.

Use the "Search" option in the left menu to search for a specific term such as the table or column description. When you already know the term, please use the "Index" option. When you can't find the information needed, please click on the Chat button at the bottom or place your question in the <link displaytype="text" defaultstyle="true" type="weblink" href="https://forums.invantive.com/">user community</link>. Invantive Support or other users will try to help you.

Wikipedia is online software for encyclopedical knowledge. Wikipedia handles both the collection, sharing and maintenance of large volumes of encyclopedical knowledge across a wide range of languages.

The Wikipedia driver covers 2 tables and 35 columns.

Wikipedia API Clients

Invantive SQL is available on many user interfaces ("clients" in traditional server-client paradigma). All Invantive SQL statements can be exchanged with a close to 100% compatibility across all clients and operating systems (Windows, MacOS, Linux, iOS, Android).

The clients include Microsoft Excel, Microsoft Power BI, Microsoft Power Query, Microsoft Word and Microsoft Outlook. Web-based clients include Invantive Cloud, Invantive Bridge Online as OData proxy, Invantive App Online for interactive apps, Online SQL Editor for query execution and Invantive Data Access Point as extended proxy.

The <link displaytype="text" defaultstyle="true" type="weblink" href="https://cloud.invantive.com/wikipedia" target="_blank" styleclass="Normal" translate="true">Wikipedia Power BI connector</link> is based on the Invantive SQL driver for Wikipedia, completed by a high-performance OData connector which works straight on Power BI without any add-on. The OData protocol is always version 4, independent whether the backing platform uses OData, SOAP or another protocol.

For technical users there are command-line editions of Invantive Data Hub running on iOS, Android, Windows, MacOS and Linux. Invantive Data Hub is also often used for enterprise server applications such as ETL. High-volume replication of data taken from the Wikipedia API into traditional databases such as SQL Server (on-premises and Azure), MySQL, PostgreSQL and Oracle is possible using <link displaytype="text" defaultstyle="true" type="weblink" href="https://data-replicator.cloud/" target="_blank" styleclass="Normal" translate="true">Invantive Data Replicator</link>. Invantive Data Replicator automatically creates and maintains Wikipedia datawarehouses, possibly in combination with data from over 75 other (cloud) platforms. Invantive Data Replicator supports data volumes up to over 1 TB and over 5.000 companies. The on-premise edition of Invantive Bridge offers an Wikipedia ADO.net provider.

Finally, online web apps can be build for Wikipedia using App Online of <link displaytype="text" defaultstyle="true" type="weblink" href="https://cloud.invantive.com/wikipedia" target="_blank" styleclass="Normal" translate="true">Invantive Cloud</link>.

Monitor API Calls

When a query or DML-statement has been executed on Invantive SQL a developer can evaluate the actual calls made to the Wikipedia API using a query on

sessionios@DataDictionary. As an alternative, extensive request and response logging can be enabled by setting log-native-calls-to-disk to true. In the %USERPROFILE% \Invantive\NativeLog folder Invantive SQL will create log files per Wikipedia API request and response.

Specificaties

The SQL driver for Wikipedia does not support partitioning. Define one data container in a database for each company in Wikipedia to enable parallel access for data from multiple companies.

Een inleiding in de concepten van Invantive SQL zoals databases, data containers en partitionering is te vinden in de <link displaytype="text" defaultstyle="true" type="weblink" href="https://go.invantive.com/sqlgrammar" target="_blank" styleclass="Normal" translate="true">Invantive SQL grammatica</link>.

The configuration can be changed using various attributes during log on and use. A full list of configuration options is listed in the driver attributes 2.

The catalog name is used to compose the full qualified name of an object like a table or view. The schema name is used to compose the full qualified name of an object like a table or view. On Wikipedia the comparison of two texts is case sensitive by default.

Changes and bug fixes on the Wikipedia SQL driver can be found in the release notes. There is currently no specific section on the Invantive forums for Wikipedia. Please reach out to other users of Wikipedia by leaving a question or contact request.

Driver code for use in settings.xml: `Wikipedia`

Alias: `wikipedia`

Aanbevolen alias: `wka`

Status: Non-production

Updated: 19-12-2022 16:43 using Invantive SQL version 22.1.113-BETA+3734.

2 SQL Driver Attributes for Wikipedia API

The SQL driver for Wikipedia has many attributes that can be finetuned to improve handling in scenarios with unreliable network connections to the API server of Wikipedia or high volumes of data. Also, many drivers have driver-specific attributes to finetune actual behaviour or handle data not matching specifications.

The Wikipedia driver attributes are assigned a default value which seldom requires change. However, changes can be applied when needed on four levels, which are reflected in the table below by separate checkmarks:

- Connection string: the connection string from the settings*.xml file and applied during log on.
- Set SQL statement: a set SQL-statement to be executed once connection has been established.
- Log on: value to be specified interactively by user during log on in a user interface.

The connection string for Wikipedia can be found in the settings*.xml file used for the database. The reference manuals contain instructions how to relocate the settings*.xml files. Settings*.xml files are typically located in the </text><text styleclass="Code Example In Regel" translate="true">%USERPROFILE%\invantive</text><text styleclass="Normal"

translate="true"> folder in most deployment scenarios. The reference manuals contain instructions how to relocate the settings*.xml files. Each data container of a database in the connection string can have a </text><text styleclass="Code Example In Regel" translate="true">connectionString</text><text styleclass="Normal" translate="true"> element specifying the name and values of attributes. Both name and value must be properly escaped according to XML-semantics. Actual application of the value is solely done during log on. A new connection must be established to change the value of a driver attribute using a connection string.

The set SQL statement can be executed after log on. The syntax is: </text><text styleclass="Code Example In Regel" translate="true">set NAME VALUE</text><text styleclass="Normal" translate="true">, or for a distributed database: </text><text styleclass="Code Example In Regel" translate="true">set NAME@ALIAS VALUE</text><text styleclass="Normal" translate="true">. In some scenarios you may need to enclose the driver attribute name in square brackets to escape it from parsing, for instance when a reserved SQL keyword is part of the name. The new value takes effect straight after execution of the set-statement. The set-statement can be executed as often as needed during a session.

Driver attributes that can be interactively set to a value are typically presented in the log on window. Depending on the platform and design decisions of the user interface designer, some or all of the available driver attributes can have been made available.

The Wikipedia driver can be configured using the following attributes:

Code	Description	Origin	Default Value	Set from Connection String	Set from Set SQL-Statement	Set from Drivers File	Set from Log On
add-odata-mandatory-filters	Whether to automatically add OData filters deemed necessary by the platform.	OData	False	✓	✓	✓	
analysis-enforce-row-uniqueness	Use for analysis only! Enforce rows to be unique.	Shared	False	✓	✓	✓	
api-url	URL to access the API.	OData		✓		✓	
bulk-delete-page-size-rows	Number of rows to delete per batch when bulk deleting	Shared	10000	✓	✓	✓	
bulk-insert-page-size-bytes	Approximate maximum size in bytes of batch when bulk inserting	Shared	10000000	✓	✓	✓	
bulk-insert-page-size-rows	Number of rows to insert per batch when bulk inserting	Shared	250	✓	✓	✓	
download-error-400-bad-request-max-tries	Maximum number of tries when OData server reports bad format during retrieval of data.		3	✓	✓	✓	
download-error-400-bad-request-sleep-initial-ms	Initial sleep in milliseconds between retries when OData server reports that the API server is unavailable during retrieval of data.		500	✓	✓	✓	
download-error-400-bad-request-sleep-max-ms	Maximum sleep in milliseconds between retries when OData server reports that the API server is unavailable during retrieval of data.		5000	✓	✓	✓	
download-error-400-bad-request-	Multiplication factor for sleep between retries OData server		2	✓	✓	✓	

Code	Description	Origin	Default Value	Set from Connection String	Set from Set SQL-Statement	Set from Drivers File	Set from Log On
sleep-multiplicator	reports that the API server is unavailable during retrieval of data.						
download-error-408-request-timeout-max-tries	Maximum number of tries when the website reports a HTTP status 408.		10	✓	✓	✓	
download-error-408-request-timeout-sleep-initial-ms	Initial sleep in milliseconds between retries when the website reports a HTTP status 408.		10000	✓	✓	✓	
download-error-408-request-timeout-sleep-max-ms	Maximum sleep in milliseconds between retries when the website reports a HTTP status 408.		300000	✓	✓	✓	
download-error-408-request-timeout-sleep-multiplicator	Multiplication factor for sleep between retries when the website reports a HTTP status 408.		2	✓	✓	✓	
download-error-422-bad-request-max-tries	Maximum number of tries when OData server reports unprocessable entity during retrieval of data.		30	✓	✓	✓	
download-error-422-bad-request-sleep-initial-ms	Initial sleep in milliseconds between retries when OData server reports unprocessable entity during retrieval of data.		10000	✓	✓	✓	
download-error-422-bad-request-sleep-max-ms	Maximum sleep in milliseconds between retries when OData server reports unprocessable entity during retrieval of data.		300000	✓	✓	✓	
download-error-422-bad-request-sleep-multiplicator	Multiplication factor for sleep between retries OData server reports unprocessable entity during retrieval of data.		2	✓	✓	✓	
download-error-429-too-many-requests-max-tries	Maximum number of tries when the website reports that too many requests have been made during a timeslot of one minute or one day.		10	✓	✓	✓	
download-error-429-too-many-requests-sleep-initial-ms	Initial sleep in milliseconds between retries when the website reports that too many requests have been made during a timeslot of one minute or one day.		10000	✓	✓	✓	
download-error-429-too-many-requests-sleep-max-ms	Maximum sleep in milliseconds between retries when the website reports that too many requests have been made during a timeslot of one minute or one day.		300000	✓	✓	✓	
download-error-429-too-many-requests-sleep-multiplicator	Multiplication factor for sleep between retries when the website reports that too many requests have been made during a timeslot of one minute or one day.		2	✓	✓	✓	
download-error-502-server-	Maximum number of tries when OData server reports a bad gateway during retrieval of data.		30	✓	✓	✓	

Code	Description	Origin	Default Value	Set from Connection String	Set from Set SQL-Statement	Set from Drivers File	Set from Log On
unavailable-max-tries							
download-error-502-server-unavailable-sleep-initial-ms	Initial sleep in milliseconds between retries when OData server reports a bad gateway during retrieval of data.		10000	✓	✓	✓	
download-error-502-server-unavailable-sleep-max-ms	Maximum sleep in milliseconds between retries when OData server reports that a bad gateway during retrieval of data.		300000	✓	✓	✓	
download-error-502-server-unavailable-sleep-multiplicator	Multiplication factor for sleep between retries OData server reports a bad gateway during retrieval of data.		2	✓	✓	✓	
download-error-503-server-unavailable-max-tries	Maximum number of tries when OData server reports that the API server is unavailable during retrieval of data.		30	✓	✓	✓	
download-error-503-server-unavailable-sleep-initial-ms	Initial sleep in milliseconds between retries when OData server reports that the API server is unavailable during retrieval of data.		10000	✓	✓	✓	
download-error-503-server-unavailable-sleep-max-ms	Maximum sleep in milliseconds between retries when OData server reports that the API server is unavailable during retrieval of data.		300000	✓	✓	✓	
download-error-503-server-unavailable-sleep-multiplicator	Multiplication factor for sleep between retries OData server reports that the API server is unavailable during retrieval of data.		2	✓	✓	✓	
download-error-504-gateway-timeout-max-tries	Maximum number of tries when the website reports a gateway timeout.		10	✓	✓	✓	
download-error-504-gateway-timeout-sleep-initial-ms	Initial sleep in milliseconds between retries when the website reports a gateway timeout.		10000	✓	✓	✓	
download-error-504-gateway-timeout-sleep-max-ms	Maximum sleep in milliseconds between retries when the website reports a gateway timeout.		300000	✓	✓	✓	
download-error-504-gateway-timeout-sleep-multiplicator	Multiplication factor for sleep between retries when the website reports a gateway timeout.		2	✓	✓	✓	
download-error-590-network-connect-timeout-max-tries	Maximum number of tries when the website reports a HTTP status 590.		10	✓	✓	✓	
download-error-590-network-	Initial sleep in milliseconds between retries when the website reports a		10000	✓	✓	✓	

Code	Description	Origin	Default Value	Set from Connection String	Set from Set SQL-Statement	Set from Drivers File	Set from Log On
connect-timeout-sleep-initial-ms	HTTP status 590.						
download-error-590-network-connect-timeout-sleep-max-ms	Maximum sleep in milliseconds between retries when the website reports a HTTP status 590.		300000	✓	✓	✓	
download-error-590-network-connect-timeout-sleep-multiplicator	Multiplication factor for sleep between retries when the website reports a HTTP status 590.		2	✓	✓	✓	
download-error-599-network-connect-timeout-max-tries	Maximum number of tries when the website reports a HTTP status 599.		10	✓	✓	✓	
download-error-599-network-connect-timeout-sleep-initial-ms	Initial sleep in milliseconds between retries when the website reports a HTTP status 599.		10000	✓	✓	✓	
download-error-599-network-connect-timeout-sleep-max-ms	Maximum sleep in milliseconds between retries when the website reports a HTTP status 599.		300000	✓	✓	✓	
download-error-599-network-connect-timeout-sleep-multiplicator	Multiplication factor for sleep between retries when the website reports a HTTP status 599.		2	✓	✓	✓	
download-error-argument-exception-max-tries	Maximum number of tries when an argument exception is returned when downloading a blob.		10	✓	✓	✓	
download-error-argument-exception-sleep-initial-ms	Initial sleep in milliseconds between retries when an argument exception is returned when downloading a blob.		10000	✓	✓	✓	
download-error-argument-exception-sleep-max-ms	Maximum sleep in milliseconds between retries when an argument exception is returned when downloading a blob.		300000	✓	✓	✓	
download-error-argument-exception-sleep-multiplicator	Multiplication factor for sleep between retries when an argument exception is returned when downloading a blob.		2	✓	✓	✓	
download-error-internet-down-max-tries	Maximum number of tries when the Internet connection seems down during retrieval of data.		10	✓	✓	✓	
download-error-internet-down-sleep-initial-ms	Initial sleep in milliseconds between retries when the Internet connection seems down during retrieval of data.		10000	✓	✓	✓	
download-error-internet-down-sleep-max-ms	Maximum sleep in milliseconds between retries when the Internet connection seems down during retrieval of data.		300000	✓	✓	✓	

Code	Description	Origin	Default Value	Set from Connection String	Set from Set SQL-Statement	Set from Drivers File	Set from Log On
download-error-internet-down-sleep-multiplicator	Multiplication factor for sleep between retries when the Internet connection seems down during retrieval of data.		2	✓	✓	✓	
download-error-io-exception-max-tries	Maximum number of tries when a network I/O connection failure occurs during retrieval of data.		10	✓	✓	✓	
download-error-io-exception-sleep-initial-ms	Initial sleep in milliseconds between retries when a network I/O connection failure occurs during retrieval of data.		10000	✓	✓	✓	
download-error-io-exception-sleep-max-ms	Maximum sleep in milliseconds between retries when a network I/O connection failure occurs during retrieval of data.		300000	✓	✓	✓	
download-error-io-exception-sleep-multiplicator	Multiplication factor for sleep between retries when a network I/O connection failure occurs during retrieval of data.		2	✓	✓	✓	
download-error-json-exception-max-tries	Maximum number of tries when an invalid JSON body is returned.		3	✓	✓	✓	
download-error-json-exception-sleep-initial-ms	Initial sleep in milliseconds between retries when an invalid JSON body is returned.		1000	✓	✓	✓	
download-error-json-exception-sleep-max-ms	Maximum sleep in milliseconds between retries when an invalid JSON body is returned.		10000	✓	✓	✓	
download-error-json-exception-sleep-multiplicator	Multiplication factor for sleep between retries when an invalid JSON body is returned.		2	✓	✓	✓	
download-error-other-exception-max-tries	Maximum number of tries when an unqualified error occurs during retrieval of data.		3	✓	✓	✓	
download-error-other-exception-sleep-initial-ms	Initial sleep in milliseconds between retries when an unqualified error ocurrs during retrieval of data.		10000	✓	✓	✓	
download-error-other-exception-sleep-max-ms	Maximum sleep in milliseconds between retries when an unqualified error ocurrs during retrieval of data.		300000	✓	✓	✓	
download-error-other-exception-sleep-multiplicator	Multiplication factor for sleep between retries when an unqualified error ocurrs during retrieval of data.		2	✓	✓	✓	
download-error-socket-exception-max-tries	Maximum number of tries when the network connection is forcible dropped during retrieval of data.		10	✓	✓	✓	
download-error-socket-exception-sleep-initial-ms	Initial sleep in milliseconds between retries when the network connection is forcible dropped during retrieval of data.		10000	✓	✓	✓	

Code	Description	Origin	Default Value	Set from Connection String	Set from Set SQL-Statement	Set from Drivers File	Set from Log On
download-error-socket-exception-sleep-max-ms	Maximum sleep in milliseconds between retries when the network connection is forcible dropped during retrieval of data.		300000	✓	✓	✓	
download-error-socket-exception-sleep-multiplicator	Multiplication factor for sleep between retries when the network connection is forcible dropped during retrieval of data.		2	✓	✓	✓	
download-error-web-exception-max-tries	Maximum number of tries when a web connection failure occurs during retrieval of data.		10	✓	✓	✓	
download-error-web-exception-sleep-initial-ms	Initial sleep in milliseconds between retries when a web connection failure occurs during retrieval of data.		10000	✓	✓	✓	
download-error-web-exception-sleep-max-ms	Maximum sleep in milliseconds between retries when a web connection failure occurs during retrieval of data.		300000	✓	✓	✓	
download-error-web-exception-sleep-multiplicator	Multiplication factor for sleep between retries when a web connection failure occurs during retrieval of data.		2	✓	✓	✓	
download-error-web-not-implemented-max-tries	Maximum number of tries when the connection reports not implemented.		1	✓	✓	✓	
download-error-web-not-implemented-sleep-initial-ms	Initial sleep in milliseconds between retries when the connection reports not implemented.		10000	✓	✓	✓	
download-error-web-not-implemented-sleep-max-ms	Maximum sleep in milliseconds between retries when the connection reports not implemented.		300000	✓	✓	✓	
download-error-web-not-implemented-sleep-multiplicator	Multiplication factor for sleep between retries when the connection reports not implemented.		2	✓	✓	✓	
download-error-web-timeout-max-tries	Maximum number of tries when the connection reports a timeout.		10	✓	✓	✓	
download-error-web-timeout-sleep-initial-ms	Initial sleep in milliseconds between retries when the connection reports a timeout.		1000	✓	✓	✓	
download-error-web-timeout-sleep-max-ms	Maximum sleep in milliseconds between retries when the connection reports a timeout.		30000	✓	✓	✓	
download-error-web-timeout-sleep-multiplicator	Multiplication factor for sleep between retries when the connection reports a timeout.		2	✓	✓	✓	

Code	Description	Origin	Default Value	Set from Connection String	Set from Set SQL-Statement	Set from Drivers File	Set from Log On
download-error-web-unauthorized-max-tries	Maximum number of tries when the connection reports an unauthorized error.		1	✓	✓	✓	
download-error-web-unauthorized-sleep-initial-ms	Initial sleep in milliseconds between retries when the connection reports an unauthorized error.		10000	✓	✓	✓	
download-error-web-unauthorized-sleep-max-ms	Maximum sleep in milliseconds between retries when the connection reports an unauthorized error.		300000	✓	✓	✓	
download-error-web-unauthorized-sleep-multiplicator	Multiplication factor for sleep between retries when the connection reports an unauthorized error.		2	✓	✓	✓	
force-case-sensitive-identifiers	Consider identifiers as case-sensitive independent of the platform capabilities.	Shared	False	✓	✓	✓	
forced-casing-identifiers	Forced casing of identifiers. Choose from Unset, Lower, Upper and Mixed.	Shared		✓	✓	✓	
http-disk-cache-compression-level	Compression level for the HTTP disk cache, ranging from 1 (little) to 9 (intense). Default is 5.	Shared	5	✓	✓	✓	
http-disk-cache-directory	Directory where HTTP cache is stored.	Shared	C:\Users\gle3.WS212\Invantive\Cache\http\gle3\shared	✓	✓	✓	
http-disk-cache-ignore-write-errors	Whether to ignore write errors to disk cache.	Shared	False	✓	✓	✓	
http-disk-cache-max-age-sec	Maximum acceptable age in seconds for use of data in the HTTP disk cache.	Shared	2592000	✓	✓	✓	
http-get-timeout-max-ms	HTTP GET maximum timeout on retry (ms).		24000	✓	✓	✓	
http-get-timeout-ms	HTTP GET timeout (ms).		56000	✓	✓	✓	
http-memory-cache-compression-level	Compression level for the HTTP memory cache, ranging from 1 (little) to 9 (intense). Default is 5.	OData	5	✓	✓	✓	
http-memory-cache-max-age-sec	Maximum acceptable age in seconds for use of data in the HTTP memory cache.	OData	14400	✓	✓	✓	
http-post-timeout-max-ms	HTTP POST maximum timeout on retry (ms).		58000	✓	✓	✓	
http-post-timeout-ms	HTTP POST timeout (ms).		57000	✓	✓	✓	
ignore-http-400-errors	Ignore HTTP 400 errors when exchanging results with the OData endpoint.		False	✓	✓	✓	

Code	Description	Origin	Default Value	Set from Connection String	Set from Set SQL-Statement	Set from Drivers File	Set from Log On
ignore-http-401-errors	Ignore HTTP 401 errors when exchanging results with the OData endpoint.		False	✓	✓	✓	
ignore-http-402-errors	Ignore HTTP 402 errors when exchanging results with the OData endpoint.		False	✓	✓	✓	
ignore-http-403-errors	Ignore HTTP 403 errors when exchanging results with the OData endpoint.		False	✓	✓	✓	
ignore-http-404-errors	Ignore HTTP 404 errors when exchanging results with the OData endpoint.		False	✓	✓	✓	
ignore-http-422-errors	Ignore HTTP 422 errors when exchanging results with the OData endpoint.		False	✓	✓	✓	
ignore-http-429-errors	Ignore HTTP 429 errors when exchanging results with the OData endpoint.		False	✓	✓	✓	
ignore-http-500-errors	Ignore HTTP 500 errors when exchanging results with the OData endpoint.		False	✓	✓	✓	
ignore-http-502-errors	Ignore HTTP 502 errors when exchanging results with the OData endpoint.		False	✓	✓	✓	
ignore-http-503-errors	Ignore HTTP 503 errors when exchanging results with the OData endpoint.		False	✓	✓	✓	
invalid-json-on-get-max-tries	Maximum number of tries when the JSON received on GET is invalid.		10	✓	✓	✓	
invalid-json-on-get-sleep-initial-ms	Initial sleep in milliseconds between retries when the JSON received on GET is invalid.		10000	✓	✓	✓	
invalid-json-on-get-sleep-max-ms	Maximum sleep in milliseconds between retries when the JSON received on GET is invalid.		300000	✓	✓	✓	
invalid-json-on-get-sleep-multiplicator	Multiplication factor for sleep between retries when the JSON received on GET is invalid.		2	✓	✓	✓	
invalid-json-on-post-max-tries	Maximum number of tries when the JSON received on POST is invalid.		1	✓	✓	✓	
invalid-json-on-post-sleep-initial-ms	Initial sleep in milliseconds between retries when the JSON received on POST is invalid.		10000	✓	✓	✓	
invalid-json-on-post-sleep-max-ms	Maximum sleep in milliseconds between retries when the JSON received on POST is invalid.		300000	✓	✓	✓	
invalid-json-on-post-sleep-multiplicator	Multiplication factor for sleep between retries when the JSON received on POST is invalid.		2	✓	✓	✓	

Code	Description	Origin	Default Value	Set from Connection String	Set from Set SQL-Statement	Set from Drivers File	Set from Log On
invantive-sql-compress-sparse-arrays	Whether to compress sparse arrays in result sets during compression.	SQL Engine V1	True	✓	✓	✓	
invantive-sql-correct-invalid-date	Whether to correct dates considered invalid since they are before 01-01-1753. When nullable, they are removed. Otherwise they are replaced by 01-01-1753.	SQL Engine V1	False	✓	✓	✓	
invantive-sql-forward-filters-to-data-containers	Whether to forward filters to data containers.	SQL Engine V1	True	✓	✓	✓	
invantive-sql-share-byte-arrays	Whether to share the memory used by identical byte arrays in result sets during compression.	SQL Engine V1	True	✓	✓	✓	
invantive-sql-share-strings	Whether to share the memory used by identical strings in result sets during compression.	SQL Engine V1	True	✓	✓	✓	
invantive-sql-shuffle-fetch-results-data-containers	Whether to shuffle results fetched from data containers.	SQL Engine V1	False	✓	✓	✓	
invantive-use-cache	Whether to cache the results of a query.	SQL Engine V1	True	✓	✓	✓	
join-set-points-per-request	Maximum number of values in a request when executing a join set.	OData	60	✓	✓	✓	
limit-partition-calls-left	Minimum number of remaining API calls on a partition towards a hard limit. When below, an error is raised.	OData	500	✓	✓	✓	
log-native-calls-to-disk-max-events	Maximum number of events to register from last activation.	Shared		✓	✓	✓	
log-native-calls-to-disk-max-seconds	Maximum number of seconds to register from last activation.	Shared		✓	✓	✓	
log-native-calls-to-disk-on-error	Registers native calls to data container backend as disk files when an error occurred.	Shared	False	✓	✓	✓	
log-native-calls-to-disk-on-success	Registers native calls to data container backend as disk files when successful.	Shared	False	✓	✓	✓	
log-native-calls-to-trace	Log native calls to data container backend on the trace.	Shared	False	✓	✓	✓	
maximum-length-identifiers	Non-default maximum length in characters of identifier names.	Shared		✓	✓	✓	
max-odata-filters	The maximum number of OData filter elements.	OData	100	✓	✓	✓	
max-url-length-accepted	The maximum accepted URL length before raising an error.	Shared	8000	✓	✓	✓	
max-url-length-desired	The maximum desired URL length.	Shared	8000	✓	✓	✓	

Code	Description	Origin	Default Value	Set from Connection String	Set from Set SQL-Statement	Set from Drivers File	Set from Log On
metadata-cache-max-age-sec	Maximum acceptable age in seconds for re-use of metadata.	OData		✓	✓	✓	
oauth-unauthorized-max-tries	Maximum number of tries when an OAuth exception occurs.	OData	2	✓	✓	✓	
oauth-unauthorized-sleep-initial-ms	Initial sleep in milliseconds between OAuth reauthentication tries when the OAuth authentication fails.	OData	10000	✓	✓	✓	
oauth-unauthorized-sleep-max-ms	Maximum sleep in milliseconds between OAuth reauthentication tries when the OAuth authentication fails.	OData	1000	✓	✓	✓	
oauth-unauthorized-sleep-multiplicator	Multiplication factor for sleep between OAuth reauthentication tries when the OAuth authentication fails.	OData	2	✓	✓	✓	
partition-slot-based-rate-limit-length-ms	Total length in ms across all slots of a partition-based rate limit.	Shared	60000	✓		✓	
partition-slot-based-rate-limit-slots	Number of slots per partition-based rate limit. Null means no slot-based rate limit	Shared		✓		✓	
pre-request-delay-ms	Pre-request delay in milliseconds per request.	Shared	0	✓	✓	✓	
requested-page-size	Preferred number of rows to exchange per round trip; only effective on limited platforms such as AFAS Online	Shared		✓	✓	✓	
requests-parallel-max	Maximum number of parallel data requests from individual partitions on the data container.	Shared	32	✓	✓	✓	
simulate-http-400-errors	Simulate HTTP 400 errors when exchanging results with the OData endpoint.		False	✓	✓	✓	
simulate-http-400-errors-percentage	Percentage of simulated HTTP 400 errors when exchanging results with the OData endpoint.		0	✓	✓	✓	
simulate-http-401-errors	Simulate HTTP 401 errors when exchanging results with the OData endpoint.		False	✓	✓	✓	
simulate-http-401-errors-percentage	Percentage of simulated HTTP 401 errors when exchanging results with the OData endpoint.		0	✓	✓	✓	
simulate-http-403-errors	Simulate HTTP 403 errors when exchanging results with the OData endpoint.		False	✓	✓	✓	
simulate-http-403-errors-percentage	Percentage of simulated HTTP 403 errors when exchanging results with the OData endpoint.		0	✓	✓	✓	
simulate-http-408-errors	Simulate HTTP 408 errors when exchanging results with the OData endpoint.		False	✓	✓	✓	

Code	Description	Origin	Default Value	Set from Connection String	Set from Set SQL-Statement	Set from Drivers File	Set from Log On
simulate-http-408-errors-percentage	Percentage of simulated HTTP 408 errors when exchanging results with the OData endpoint.		0	✓	✓	✓	
simulate-http-429-errors	Simulate HTTP 429 errors when exchanging results with the OData endpoint.		False	✓	✓	✓	
simulate-http-429-errors-percentage	Percentage of simulated HTTP 429 errors when exchanging results with the OData endpoint.		0	✓	✓	✓	
simulate-http-500-errors	Simulate HTTP 500 errors when exchanging results with the OData endpoint.		False	✓	✓	✓	
simulate-http-500-errors-percentage	Percentage of simulated HTTP 500 errors when exchanging results with the OData endpoint.		0	✓	✓	✓	
simulate-http-502-errors	Simulate HTTP 502 errors when exchanging results with the OData endpoint.		False	✓	✓	✓	
simulate-http-502-errors-percentage	Percentage of simulated HTTP 502 errors when exchanging results with the OData endpoint.		0	✓	✓	✓	
simulate-http-503-errors	Simulate HTTP 503 errors when exchanging results with the OData endpoint.		False	✓	✓	✓	
simulate-http-503-errors-percentage	Percentage of simulated HTTP 503 errors when exchanging results with the OData endpoint.		0	✓	✓	✓	
simulate-http-protocol-errors	Simulate HTTP protocol errors when exchanging results with the OData endpoint.		False	✓	✓	✓	
simulate-http-protocol-errors-percentage	Percentage of simulated HTTP protocol errors when exchanging results with the OData endpoint.		0	✓	✓	✓	
simulate-http-timeout-errors	Simulate HTTP timeout errors when exchanging results with the OData endpoint.		False	✓	✓	✓	
simulate-http-timeout-errors-percentage	Percentage of simulated HTTP timeout errors when exchanging results with the OData endpoint.		0	✓	✓	✓	
slot-based-rate-limit-length-ms	Total length in ms across all slots of a slot-based rate limit.	Shared	60000	✓		✓	
slot-based-rate-limit-slots	Number of slots of a slot-based rate limit. Null means no slot-based rate limit	Shared		✓		✓	
standardize-identifiers	Rewrite all identifiers to the preferred standards as configured by standardize-identifiers-casing and maximum-length-identifiers.	Shared	True	✓	✓	✓	
standardize-identifiers-casing	Rewrite all identifiers to the recommended standard platform-	Shared	True	✓	✓	✓	

Code	Description	Origin	Default Value	Set from Connection String	Set from Set SQL-Statement	Set from Drivers File	Set from Log On
	specific casing when changing a data model on a case-dependent platform.						
use-batch-insert	Whether to use batch insert.	OData	True	✓	✓	✓	
use-http-disk-cache-read	Whether to use HTTP responses from previous queries stored on disk to answer the current query.	Shared	False	✓	✓	✓	
use-http-disk-cache-write	Whether to memorize HTTP responses on disk.	Shared	False	✓	✓	✓	
use-http-memory-cache-read	Whether to use HTTP responses from previous queries stored in memory that can answer the current query.	OData	True	✓	✓	✓	
use-http-memory-cache-write	Whether to memorize HTTP responses from previous queries for use by future queries.	OData	True	✓	✓	✓	

3 Schema: Native

3.1 Tables

3.1.1 NATIVEPLATFORMSCALARREQUESTS: Wikipedia Native Platform Scalar Requests

Direct access to native API.

Catalog: Wikipedia

Schema: Native

Alias: `npt`

Label: Native Platform Scalar Requests

Documentation:

The NativePlatformScalarRequests table provides direct access to the native API protocol over an established connection to the Wikipedia API server. It will contain a new row for every row inserted with a native API request in PAYLOAD_TEXT with the results of unaltered forwarding of the payload to the Wikipedia API server.

Retrieve: true

Insert: true

Update: false

Delete: false

View Columns

The columns of the view NATIVEPLATFORMSCALARREQUESTS are shown below. Each column has an SQL data type. A new non-null value must be provided for every required column at all times during insert.

Name	Data Type	Label	Required	Documentation
BLOB_PREFERRED	boolean	BLOB Preferred	☑	Indicator whether a BLOB result is preferred over text.
BOL_RESPONSE_CACHE_MAX_AGE_SEC	int32	Response Cache Maximum Age (sec)	☐	Maximum age in seconds of Bridge Online response cache entries to be used.
CONTENT_TYPE	string(240)	Content Type	☐	
DATE_ENDED	datetime	End Date	☑	
DATE_STARTED	datetime	Start Date	☑	
DRY_RUN	boolean	Run without Actions	☑	
DURATION_MS	int32	Duration (ms)	☑	
ERROR_MESSAGE_CODE	string(30)	Error Message Code	☐	
ERROR_MESSAGE_TEXT	string(32000)	Error Message Text	☐	
FAIL_ON_ERROR	boolean	Fail on Error	☑	Whether to raise an exception when processing the native request triggered an error from the provider.
HTTP_DISK_CACHE_MAX_AGE_SEC	int32	HTTP Disk Cache Maximum Age (sec)	☐	Maximum age in seconds of HTTP disk cache entries to be used.
HTTP_DISK_CACHE_SAVE	boolean	Save HTTP Disk Cache	☐	Whether results can be stored in HTTP disk cache.
HTTP_DISK_CACHE_USE	boolean	Use HTTP Disk Cache	☐	Whether results can be fetched from HTTP disk cache.
HTTP_MEMORY_CACHE_MAX_AGE_SEC	int32	HTTP Memory Cache Maximum Age (sec)	☐	Maximum age in seconds of HTTP memory cache entries to be used.
HTTP_MEMORY_CACHE_SAVE	boolean	Save HTTP Memory Cache	☐	Whether results can be stored in HTTP memory cache.
HTTP_MEMORY_CACHE_USE	boolean	Use HTTP Memory Cache	☐	Whether results can be fetched from HTTP memory cache.
HTTP_METHOD	string(30)	HTTP Method	☐	
HTTP_STATUS_CODE	int16	HTTP Status Code	☐	
ORIG_SYSTEM_GROUP	string(4000)	Original System Group	☐	
ORIG_SYSTEM_REFERENCE	string(4000)	Original System Reference	☐	
PAYLOAD_TEXT	string	Payload	☐	
RESULT_BLOB	byte[]	Result BLOB	☐	
RESULT_DATE_TIME_UTC	datetime	Result Date Time	☐	
RESULT_NUMBER	decimal	Result Number	☐	
RESULT_TEXT	string	Result Text	☐	
SUCCESSFUL	boolean	Succesful	☑	
TIMEOUT_SEC	int32	Timeout (sec)	☐	Timeout in seconds.
TRANSACTION_ID	int32	Transaction ID	☑	Incrementing ID of the transaction.
URL	string(4000)	URL	☐	

4 Schema: Wikipedia

4.1 Tables

4.1.1 search

Catalog: Wikipedia

Schema: Wikipedia

Primary Keys: id

This is a read-only table function. The Wikipedia API may not support changing the data or the Invantive SQL driver for Wikipedia does not cover it. In the latter case, please use the table NativePlatformScalarRequests to upload data to the Wikipedia API.

Select Wikipedia API URL: `/search/page?limit=100`

Insert Wikipedia API URL: `/search/page?limit=100`

Update Wikipedia API URL: `/search/page?limit=100`

Delete Wikipedia API URL: `/search/page?limit=100`

Field Selection Method: NotRequired

Base Path: `pages[*]`

Parameters of Table Function

The following parameters can be used to control the behaviour of the table function search. A value must be provided at all times for required parameters, but optional parameters in general do not need to have a value and the execution will default to a pre-defined behaviour. Values can be specified by position and by name. In both cases, all parameters not specified will be evaluated using their default values.

Value specification by position is done by listing all values from the first to the last needed value. For example: a `select * from table(value1, value2, value3)` on a table with four parameters will use the default value for the fourth parameter and the specified values for the first three.

Value specification by name is done by listing all values that require a value. For example with `select * from table(name1 => value1, name3 => value3)` on the same table will use the default values for the second and fourth parameters and the specified values for the first and third.

Name	Data Type	Required	Default Value	Documentation
q	string	☑		

Columns of Table Function

The columns of the table function search are shown below. Each column has an SQL data type.

Name	Data Type	Label	Required	Documentation
description	string		☐	
excerpt	string		☐	
id	int64		☑	

Name	Data Type	Label	Required	Documentation
key	string		☑	
matched_title	string		☐	
title	string		☑	

Index

- A -

- B -

- C -

- D -

- E -

- F -

- H -

- I -

- J -

- K -

- L -

- M -

- N -

- O -

- P -

- Q -

- R -

- S -

- T -

- U -

- W -

Invantive B.V.
Biesteweg 11
3849 RD Hierden
the Netherlands

Tel: +31 88 00 26 500
Fax: +31 84 22 58 178
info@invantive.com
invantive.com

IBAN NL25 BUNQ 2098 2586 07
Chamber of Industry and Commerce
13031406
VAT NL812602377B01
RSIN 8122602377
Managing Director: Guido Leenders
Registered office: Roermond

24.0.92
28/05/2026, 20:16
ISBN 978-94-6302-000-8: